

AKARI IRC Data User Manual for Post-Helium (Phase 3) Mission

Version 1.1

Takashi Onaka¹, Rosario Lorente², Yoshifusa Ita³, Youichi Ohyama⁴,
Toshihiko Tanabé¹, and Chris Pearson⁵

with contributions from:

Martin Cohen⁶, Daisuke Ishihara¹, Itsuki Sakon¹, Takehiko Wada⁷,
Issei Yamamura⁷, and Hideo Matsuhara⁷

¹The University of Tokyo, Japan

²European Space Astronomy Centre (ESAC), ESA

³National Astronomical Observatory, Japan (NAOJ)

⁴Academia Sinica Institute of Astronomy & Astrophysics, Taiwan (ASIAA)

⁵Rutherford Appleton Laboratory (RAL), U.K.

⁶University of California, Berkeley, U.S.A.

⁷Institute of Space and Astronautical Science (ISAS), JAXA, Japan

August 28, 2009



Date	Revision	Comments
30 January 2009	Version 0.9	copy from IDUM 1.4
7 March 2009	Version 1.0	Revisions completed
24 August 2009	Version 1.1	Table 4.6.4 corrected

Contents

1	Introduction	1
1.1	Purpose of this document	1
1.2	Relevant information	1
2	Instrument overview	3
2.1	Focal plane arrays	4
2.1.1	Near-InfraRed Camera: NIR	4
2.1.2	Arrays operation	7
2.2	Instrument AOTs	7
2.2.1	IRCZ0	8
2.2.2	IRCZ2	8
2.2.3	IRCZ3	8
2.2.4	IRCZ4	8
2.3	In-orbit sensitivity	8
3	Distributed Data Products	11
3.1	IRC FITS file naming rule	11
3.2	Raw data description	11
3.2.1	Raw data naming convention	11
3.2.2	AKARI FITS Primary HDU (common information) rawdata header . . .	12
3.2.3	Raw data dimensions	15
3.3	Quick look data	16
3.3.1	IRC imaging IRCZ0, IRCZ2 and IRCZ3	16
3.3.2	IRC spectroscopy: IRCZ4	16
3.4	IRCZ4 image orientation and dispersion direction	17
4	IRC Calibration and Accuracy	19
4.1	Dark image	19
4.2	Flatfield	19
4.2.1	Flatfields for imaging data	19
4.2.2	Flats for spectroscopy images	20
4.3	Instrument linearity	20
4.4	Instrument Point Spread Function	20
4.5	RSRF	21
4.6	Flux calibration for point sources	21
4.6.1	Estimation of the in-band flux	22
4.6.2	Absolute calibration	23
4.6.3	Stability of the sensitivity	23
4.7	Flux calibration for extended sources	23
4.8	Color correction	24

4.9	Pixel scale	28
4.10	Astrometry	28
4.11	Arrays anomalies	28
4.12	General concerns on slit-less spectroscopy data	28
5	Imaging toolkit cookbook	32
5.1	Introduction	32
5.2	General overview of the toolkit processing	32
5.3	Expected Data Processing Rate (minimum expectation)	33
5.4	How to install the IRC imaging Toolkit	34
5.4.1	Requirements	34
5.4.2	Install IRAF	34
5.4.3	Download IRC imaging data reduction software package	34
5.4.4	Unpack irc_p3.tgz	34
5.4.5	Make irc binaries	34
5.4.6	Run "setpath.pl"	34
5.4.7	Perl path	35
5.4.8	Add IRC_P3 entry to IRAF	35
5.5	How to UPGRADE the version of IRC_P3 imaging toolkit	36
5.6	Setting up your toolkit environment and running the pipeline	36
5.6.1	Creating the directory structure	36
5.6.2	Launch IRAF	37
5.6.3	Load the IRC_P3 package	37
5.7	The pre-pipeline processor (Red-Box)	39
5.7.1	Configuration	39
5.7.2	Running the prepipeline processor	39
5.8	Before running the pipeline processor	42
5.9	The pipeline processor (Green-Box)	43
5.9.1	Configuration	43
5.9.2	Running Green-Box pipeline module	45
5.10	The pipeline processor (Blue-Box): bluebox.coadd wrapper Module	49
5.10.1	The Blue-Box Co-Add Wrapper	49
5.10.2	Log files produced from the toolkit	53
5.11	Toolkit structure	54
5.12	Working on the output	55
5.13	Limitations of the functionalities in the current version of the imaging toolkit	55
5.13.1	Instrumental characteristics and artefacts in the data	55
5.13.2	Toolkit Limitations and Caveats	56
5.14	Error messages when running the pipeline and Troubleshooting	56
6	Spectroscopy pipeline cookbook	59
6.1	General overview of the pipeline processing	59
6.1.1	Dark subtraction	60
6.1.2	Linearity correction/Saturation Masking	60
6.1.3	(monochromatic) Flat-fielding	60
6.1.4	Background subtraction (from individual sub-frames)	61
6.1.5	Image screening	61
6.1.6	Image registration (among sub-frames)	61
6.1.7	Imaging stacking	61
6.1.8	Target detection/position measurement	62

6.1.9	Background subtraction (from stacked image)	62
6.1.10	Extracting 2D spectra	62
6.1.11	Wavelength calibration	63
6.1.12	Flat color-term correction	64
6.1.13	(local) Background subtraction (from extracted 2D spectra)	64
6.1.14	Spectral tilt correction	65
6.1.15	Spectral response calibration	65
6.1.16	Notes on slit spectroscopy	65
6.2	How to install and to set-up the IRC spectroscopy pipeline	65
6.2.1	Data preparation	66
6.3	Calibration data	66
6.3.1	Calibration files	66
6.4	Running the pipeline	69
6.4.1	Data reduction order	69
6.4.2	Running the pipeline	69
6.4.3	Options	71
6.4.4	Outputs	72
6.4.5	Summary of interactive operations within the pipeline	74
6.4.6	Warning messages of the pipeline	74
6.5	Working on the pipeline output	76
6.5.1	Displaying the whole images on ds9	76
6.5.2	Displaying the extracted images on ATV	76
6.5.3	Checking for wavelength zero reference point with the zero-th order light image	77
6.5.4	Spectral plotting tool	78
6.5.5	Working on saved data	80
6.6	(Hopefully) Useful Tips	80
6.6.1	Getting best S/N spectra in slit (Ns, Nh) or Np spectroscopy data	80
6.6.2	Tackling narrow spikes seen in NIR spectra (especially in slit spectra)	80
6.6.3	Examining strange/fake features in NP spectra, especially around 2.4-3.5 μm	81
6.6.4	Examining flux level (in)consistency among different disperser data	81
6.7	Appendix	82
6.7.1	Variable name conventions	82
6.7.2	Summary of Commands and their Options	83
6.8	Error messages when running the pipeline and Troubleshooting	85
6.9	Tips for the Phase 3 data reduction	87
6.9.1	AOT IRCZ4	87
6.9.2	Spectroscopic performance	87
6.9.3	Dark current, linearity, and hot pixels	87
6.9.4	Response	87
6.9.5	New options for the phase 3 data reduction	88
6.9.6	Installation and usage of the toolkit for phase 3	88
6.9.7	Known problems	89

Chapter 1

Introduction

1.1 Purpose of this document

This document is intended to provide a comprehensive guide to data taken during the post-Helium (hereafter phase 3) mission with the Infrared Camera (IRC) onboard AKARI for observers to get started quickly. It includes a brief summary of the instrumentation, a summary of the data products, and the pipeline software overview together with the calibration of the instrument. Part of the data and information given here will be updated as the data reduction and calibration will get improved. The latest information may be posted on the web till the revised version will be prepared. A comprehensive overview of the instrumentation and operation is described in the AKARI IRC Data User Manual and is given in the AKARI first result volume (Publications of the Japanese Astronomical Society volume 59, No. SP2). Also see the AKARI Observer's Manual for the Post-Helium (Phase 3) Mission.

1.2 Relevant information

AKARI Observer's Web

The ISAS Web page contains the most up to date information:

URL:<http://www.ir.isas.jaxa.jp/AKARI/Observation/>

The ESAC page also includes up to date information:

URL:<http://akari.esac.esa.int/observers/>

Helpdesk

Any questions and comments on AKARI observations and user support are addressed to the AKARI Helpdesks:

iris_help@ir.isas.jaxa.jp

<http://akari.esac.esa.int/esupport/>

Chapter 2

Instrument overview

The Infrared Camera (IRC) onboard AKARI was originally designed to make wide-field deep imaging and low-resolution spectroscopic observations in the pointing mode of the AKARI satellite. Its unique wide field coverage of 10×10 arcmin² is ideal for survey-type observations or multi-object spectroscopic programs.

The capability for the use in the survey mode has later been explored and now is also being used to carry out mid-infrared all-sky survey observations.

Each channel has a filter wheel, on which medium band filters, dispersive elements, and a blank window as a shutter are installed. Table 2.0.1 summarizes the parameters of the IRC filters and dispersion elements. The NIR camera covers three independent wavelength bands that very roughly correspond to the well known K, L, and M bands. Each of the two MIR cameras have two narrow filters which cover the shorter and longer half of the wavelength range of the cameras, and a wide filter that overlaps the two narrow filters. The S9W and L18W bands are used for the all-sky survey observations,

In the phase 3 mission, only the NIR camera is working and the MIR cameras are turned off. In the followings however, some description of the MIR cameras is also given.

The pixel scale and the imaging area of the focal plane arrays are summarized in Table 2.0.2. The imaging area is the rectangular area excluding the slit region.

The dispersion elements of the IRC are set into the filter wheel so that all the light in the FoV is dispersed. A spectrum is obtained in the direction parallel to the scan path (in-scan direction). Slits are provided for each camera (Figure 2.0.2) in order to avoid contamination by nearby sources / diffuse radiation. The two dispersion elements of the NIR camera provide different spectral resolutions over a similar wavelength range.

The slits are primarily designed for extended sources and it should not be assumed that they can be used to guide a point source into the slit, except for the NIR camera which has an aperture for point sources. The current design is the following:

- The slit for the NIR camera consists of three parts of different widths. The left most (closest to the imaging area) has a 5 arcsec width and will be mainly used for simultaneous observations of diffuse light with the MIR-S camera. This slit position is labeled as ‘Ns’ for IRC04 AOT observation parameter. Both the NP (low-resolution prism) and NG (high-resolution grism) will be used with this slit. The middle $1' \times 1'$ square part, referred to as ‘Np’ is for spectroscopy of point sources. The aperture is large compared to the absolute pointing accuracy of the satellite (designed to be better than 30 arcsec) to ensure that the target can be accurately guided into the area. Note that for observations of faint sources, confusion due to galaxies may be a serious problem. The NG (grism) is assumed to be used with this aperture. The rightmost (outer) part (‘Nh’) has a 3 arcsec width and is used for the highest resolution spectroscopy of diffuse radiation with the NG (grism).




Figure 2.0.1: Bird's-eye view of the IRC camera.

2.1 Focal plane arrays

The IRC comprises three channels (Fig 2.0.1). The near-infrared (NIR) channel operates in 2-5 μm , the mid-infrared short (MIR-S) channel covers 5-12 μm , and the mid-infrared long (MIR-L) channel works in 12-26 μm . The NIR uses 512 \times 412 format InSb array and MIR-S and MIR-L both employ 256 \times 256 format Si:As impurity band conduction arrays. The three channels have a field of view of about 10' \times 10' and the NIR and MIR-S share the same field of view by the beam splitter, whereas the MIR-L observes a sky about 25' away from the NIR/MIR-S sky (Figure 2.0.2).

2.1.1 Near-InfraRed Camera: NIR

Figure 2.1.3 shows the side view of the NIR channel. The light from the telescope is split by a germanium beam splitter and the near-infrared radiation is introduced to the NIR channel. The NIR consists of silicon and germanium lenses. There are color aberrations among N2, N3,




Figure 2.0.2: Field of view location of the three channels of the IRC. The vertical arrow indicates the scan direction in the survey mode. The NIR and MIR-S share the same field of view by means of a beam splitter. See text for the usage of the slits.




Figure 2.1.3: Side-view of the NIR channel.

and N4 and the telescope focus is adjusted in between them. Faint ghosts of bright sources are also present, which come from internal reflections in the beam splitter. The brightness is about 0.7% of the true source and the position is well determined and in a good agreement with the ray-tracing simulation. There are also ghosts that seem to come from the internal scattering in

Table 2.0.1: IRC Filters and Dispersion Elements

(1) Channel	(2) Name	(3)	(4) λ_{ref} (μm)	(5) Wavelength (μm)	(6) λ_c (μm)	(7) $\Delta\lambda$ ($\mu\text{m}/\text{pix}$)	(8) Dispersion ($\mu\text{m}/\text{pix}$)
NIR	N2	filter	2.4	1.9–2.8	2.34	0.71	—
	N3	filter	3.2	2.7–3.8	3.19	0.87	—
	N4	filter	4.1	3.6–5.3	4.33	1.53	—
	NP	prism		1.8–5.2	—	—	0.06 @3.5 μm
	NG	grism		2.5–5.0	—	—	0.0097
MIR-S	S7	filter	7.0	5.9–8.4	7.12	1.75	—
	S9W	filter	9.0	6.7–11.6	8.61	4.10	—
	S11	filter	11.0	8.5–13.1	10.45	4.12	—
	SG1	grism		5.4–8.4	—	—	0.057
	SG2	grism		7.5–12.9	—	—	0.099
MIR-L	L15	filter	15.0	12.6–19.4	15.58	5.98	—
	L18W ¹	filter	18.0	13.9–25.6	18.39	9.97	—
	L24	filter	24.0	20.3–26.5	22.89	5.34	—
	LG2	grism		17.5–25.7	—	—	0.175

(4) Reference wavelength.

(5) Defined as where the responsivity for a given energy is larger than $1/e$ of the peak.

(6) Isophotal wavelength of the filter band.

(7) Effective bandwidth.

(8) Dispersion power of NP depends on wavelength.

The quoted value corresponds to $3.5\mu\text{m}$

¹Renamed from L20W. No change of the wavelength profile itself.

Table 2.0.2: General characteristics of the IRC focal plane arrays

Channel	NIR	MIR-S	MIR-L
Detector	InSb (SBRC-189)	Si:As (CRC-744)	Si:As (CRC-744)
Format	512×512	256×256	256×256
Pixel scale (")	1.46×1.46	2.34×2.34	2.51×2.39
Imaging area (pixel ²)	391×412	233×256	246×239
Readout noise (e^-)	30.6 ^a	14.2 ^b	same as MIR-S
Dark current (e^-/s)	0.2	26	same as MIR-S
Operability(%) ^c	99.9	100	100

a Estimated by Fowler 1 sampling

b Estimated by Fowler 4 sampling

c Pre-launch performance

the NIR optics. Details are under investigation.

NIR and MIR-S channels acts as a folding mirror for the MIR-S.

astigmatism. Thus the pixel scale of the MIR-L channel is not the same for the X and Y directions.

2.1.2 Arrays operation

The focal plane arrays are operated in a synchronized manner. The array operation is made in a unit frame, which consists of short and long exposures. The short exposure is intended to increase the dynamic range by about 8 to 10 times. However, data taken in the short exposure indicate anomalous behavior and at present the short-exposure data are not able to be calibrated. The clock pattern of one frame is the same for all AOTs. One frame is about 63 sec, in which NIR has one short and one long exposures. The short exposure is made with the Fowler 1 sampling scheme.

2.2 Instrument AOTs

In a pointed observation, the filter and dithering combinations for IRC have been fixed to a few patterns, which are called Astronomical Observation Template (AOT). The duration of a pointed observation and the frame time are well determined. Each AOT consists of a combination of frames of the IRC operation with dithering and filter wheel rotation operations, which is well fixed in a pointed observation. The AOTs in phase 3 are designated by AOTZ#. Figure 2.2.4 shows an illustration of the pre-fixed sequences in each AOT. In all the AOTs, except for AOT11, a dark frame is carried out before and after the observation (pre-dark and post-dark observations).

In a pointed staring observation, the IRC observation is started once it receives the notification of the stabilization of the attitude from the attitude and orbital controlling system. The IRC observation continues till the angle between the telescope axis and the earth rim becomes less than a certain value. Thus the last image in a pointed observation may be taken during the maneuver and cannot be used for astronomical observations. This will be correctly treated in the pipeline software.




Figure 2.2.4: Observation sequences of the AOT IRCZ0, Z2, Z3, and Z4. Yellow boxes labeled as “Exposure cycle” indicate exposure frames. Orange boxes with “M” are Micro-Scan operations including stabilization, and light-blue boxes with “W” are Filter Wheel rotations. Dead time for a Filter Wheel change depends on the relative position of the elements. The Green area on the right side is the extra observation time which is not guaranteed.

Table 2.3.3: IRC sensitivity and image quality

	N2	N3	N4
$5\text{-}\sigma$ sensitivity (μJy)			
AOTZ0	18	18	18
AOTZ2		31	31
AOTZ3	39	39	38

2.2.1 IRCZ0

The IRCZ0 mode was designed for deep imaging observations.

2.2.2 IRCZ2

The IRC02 mode was designed for general purpose imaging observations that take images with two fixed filters in a pointed observation. It provides at least three images for a filter with dithering operations.

2.2.3 IRCZ3

The IRCZ3 mode was designed for general purpose imaging observations that take images with three filters in a pointed observation. For each filter two imaging observations are made with dithering operations.

2.2.4 IRCZ4

The IRC04 mode was designed for general purpose spectroscopic observations. This mode does not have dithering operations. It has an imaging observation sandwiched by spectroscopic observations (observations with the dispersive elements) of 4 frames. The imaging observation will be used to determine the wavelength reference point for slit-less spectroscopy.

2.3 In-orbit sensitivity

Optical throughputs of all IRC channels are confirmed to be as expected by observations of standard stars.

The sensitivity values for the imaging AOTs are collected in Table 2.3.3.

In the case of IRCZ4, Figures 2.3.5 and 2.3.6 show the 5σ sensitivity for point and diffuse sources, respectively, as a function of λ .




Figure 2.3.5: 5σ detection limits for point sources with NP or NG in IRCZ4 with the Ns slit.




Figure 2.3.6: 5σ detection limits for diffuse sources with NP or NG in IRCZ4

Chapter 3

Distributed Data Products

Two levels of data products are delivered to the users: raw data and processed data. The raw data are intended to be used to run the pipelines described in Chapters 5 and 6 to get interactively the best science out of them. The quick look data are merely a rough approximation of what the user will get from his observations. They are the result of running the pipeline automatically and with a default setting. An interactive and fine-tuned run of the pipeline is recommended in order to improve the quality of the results.

The quick look data header contain the version of the pipeline used. Since it is continuously evolving it could be different from the version made available to the users.

3.1 IRC FITS file naming rule

Pointed observation data are distributed to the users as a tar+gz package format (hereafter 'data package') per observation. A data package contains FITS format observation data and a Readme file describing the contents etc.

During the prioritized data use period data packages are encrypted and compressed by gpg (GnuPG) program.

The naming convention for the IRC package is:

AKARLIRC_TargetID_SubID.tar.gpg

where TargetID is a 7 digits number and SubID is a 3 digits number given by the observation database.

Combination of TargetID and SubID give a unique identification of the observation.

When extracting an IRC data package a directory named AKARLIRC_TargetID_SubID/ is created. Two subdirectories, rawdata/ and irc_ql/ contain the raw FITS data files and the processed result files, respectively.

3.2 Raw data description

3.2.1 Raw data naming convention

The naming convention for the IRC raw data files is common for all the IRC AOTs and it is the following:

FVVxxxxxx_[N—M].fits

where:

- F is a fixed character
- VVVxxxxxx: Extended frame counter (decimal digits). This is a unique identifier of the exposure.

- xxxxxx: frame center in the telemetry file.
- VVV: maintained by the FITS creation program. Incremented when xxxxxx is reset to 0.

N—M : NIR / MIR (Scan mode data may have extra characters to this).

NIR data is in a separate file, while MIR-S and MIR-L are stored in the same FITS file. The README file describes:

- file list in the data package
- observation summary extracted from the FITS file
- comments specific for the observation

3.2.2 AKARI FITS Primary HDU (common information) rawdata header

The contents of the AKARI FITS Primary HDU of all raw data, both IRC and FIS, is as follows:

SIMPLE	=	T	/	Standard FITS format
BITPIX	=	16	/	number of bits per data pixel
NAXIS	=	3	/	Number of axes
NAXIS1	=	412	/	Image dimension
NAXIS2	=	512	/	Image dimension
NAXIS3	=	2	/	Image frame
EXTEND	=	T	/	Extension may be present
FMTTYPE	=	'ASTRO-F IMAGE IRC'	/	Type of File Format in FITS file
FSTYPEVER	=	4	/	Version of FMTTYPE
CNTTYPE	=	'IRC_NIR'	/	Type of data content
DATE	=	'2006-09-25T09:45:24'	/	File Creation Date
CREATOR	=	'TBD'	/	Data generator program name
CRTRVER	=	'1.0'	/	Version of CREATOR
PIPELINE	=	'ircpl ver. 1.0'	/	Data Processing Pipeline name
DATASTAT	=	'GOOD'	/	Data status
ORIGIN	=	'ISAS/JAXA'	/	Organization creating FITS file
TELESCOP	=	'AKARI'	/	AKARI mission
INSTRUME	=	'IRC'	/	Identifier of the instrument
DETECTOR	=	'NIR'	/	Detector name
OBSERVER	=	'PI Name'	/	PI Name (Observer's ID)
PROPOSAL	=	'PRPID'	/	Proposal ID
OBS-CAT	=	'OT'	/	Observation Category
PNTNG-ID	=	1234567	/	Pointing ID
TARGETID	=	1234567	/	Target ID
SUBID	=	1	/	Sub ID
OBJECT	=	'target'	/	Object name
OBJ-RA	=	320.5533	/	[degree] Target position
OBJ-DEC	=	-23.3325	/	[degree] Target position
AOT	=	'IRC03'	/	Observation AOT
AOTPARAM	=	'8;0.5;70'	/	AOT Parameter
INSTMODE	=	TBD	/	Instrument operation mode
TIMESYS	=	'UTC'	/	Explicit time scale specification

DATE-OBS	=	YYYY-MM-DDTHH:MM:SS	/	Observation start date+time
DATE-END	=	YYYY-MM-DDTHH:MM:SS	/	Observation end date+time
DATE-REF	=	YYYY-MM-DDTHH:MM:SS	/	Reference time in the Observation
AFTM-OBS	=	[double]	/	DATE-OBS in ASTRO-F Time
AFTM-END	=	[double]	/	DATE-END in ASTRO-F Time
AFTM-REF	=	[double]	/	DATE-REF in ASTRO-F Time
PIMTIOBS	=	'0xXXXXXX '	/	DATE-OBS in PIM-TI (36 bits DHUTI)
PIMTIEND	=	'0xXXXXXX '	/	DATE-END in PIM-TI (36 bits DHUTI)
PIMTIREF	=	'0xXXXXXX '	/	DATE-REF in PIM-TI (36 bits DHUTI)
EQUINOX	=	2000.0000	/	Epoch of Coordinate
RA	=	320.5533	/	[degree] Target position at DATE-REF
DEC	=	-23.3325	/	[degree] Target position at DATE-REF
ROLL	=	-30.553	/	[degree] Roll Angle at DATE-REF
AA-SOL	=	90.0021	/	[degree] Solar avoidance Angle at DATE-REF
AA-EAR	=	180.2083	/	[degree] Earth avoidance Angle at DATE-REF
AA-LUN	=	210.6821	/	[degree] Lunar avoidance Angle at DATE-REF
TM-SAA	=	1829.	/	[sec] Duration since last SAA at DATE-REF
SAT-POSX	=	2903.5528	/	[km] Satellite position at DATE-REF
SAT-POSY	=	1704.3092	/	[km] Satellite position at DATE-REF
SAT-POSZ	=	1968.4286	/	[km] Satellite position at DATE-REF
DAYNIGHT	=	'DAY '	/	Day/night status at DATE-REF
STTA-NUM	=	4	/	number of tracked stars in STT-A at DATE-REF
STTB-NUM	=	4	/	number of tracked stars in STT-B at DATE-REF
STTA-MOD	=	'TRK '	/	STT-A Mode status at DATE-REF
STTB-MOD	=	'TRK '	/	STT-B Mode status at DATE-REF
COMMENT			/	Any strings
HISTORY			/	Any strings
END				

The header keywords are sorted as follows:

- FITS basic information, data size information
 - SIMPLE refers to the standard FITS format
 - BITPIX is the number of bits per data pixel, and equal to 16 in the case of IRC
 - NAXIS is the number of axes, equal to 3 for IRC
 - NAXIS1 and NAXIS2 are the image dimensions
 - NAXIS3 is the number of image frames
 - EXTEND refers to the presence of extensions in the FITS file
- Data type, creation and processing information
 - FMTCYPE is the type of File Format in FITS file. It can be 'ASTRO-F IMAGE IRC' or 'ASTRO-F SCAN IRC'
 - FTYPEVER is the version of the file format described in FMTCYPE
 - CNTTYPE is the type of data content. It can be 'IRC_NIR' or 'IRC_MIR'
 - DATE is the file Creation Date
 - CREATOR is the data generator program name.
 - CRTRVER is the version of CREATOR. Contents TBD

- PIPELINE is the Data Processing Pipeline name and version
- DATASTAT is the Data status. It describes data status mainly from completeness of telemetry data. This does not tell detailed scientific quality of the data All appropriate error status are listed, otherwise GOOD is given GOOD: No problem INCOMPLETE: (Scientific data) incomplete due to telemetry loss etc. NOHK: HK Status not available NOADS: Attitude information not available STTINI: STT did not work properly. More status may be added as analysis progresses. Data other than GOOD may not be in the archive at the first stage.
- instrument information
 - ORIGIN is the organization creating FITS file
 - TELESCOP is the AKARI mission [Satellite Name]
 - INSTRUME is the Identifier of the instrument
 - DETECTOR is the detector name, either 'NIR' or 'MIR'
- observation details
 - OBSERVER is the PI Name (Observer's ID)
 - PROPOSAL is the Proposal ID
 - OBS-CAT is Observation Category, either 'LS', 'MP', 'OT', 'DT', 'CAL' or 'ENG'
 - PNTNG-ID is the Pointing ID. Usually it is identical with the Target ID, but is different for 'parallel mode' observations.
 - TARGETID is the Target ID
 - SUBID is the Target Sub ID
 - OBJECT is the Object name
 - OBJ-RA is the RA Target position in degrees recorded in the database (double precision)
 - OBJ-DEC is the DEC Target position in degrees recorded in the database (double precision)
 - AOT is the Observation AOT
 - AOTPARAM is the AOT Parameters set
 - INSTMODE is the Instrument operation mode. Contents TBD
 - TIMESYS is the Time system used in this file
 - DATE-OBS is the Observation start date+time, with format YYYY-MM-DDTHH:MM:SS
 - DATE-END is the Observation end date+time. Same format than above
 - DATE-REF is the Reference time in the Observation. Same format than above
 - AFTM-OBS is the DATE-OBS in ASTRO-F Time
 - AFTM-END is the DATE-END in ASTRO-F Time
 - AFTM-REF is the DATE-REF in ASTRO-F Time
 - PIMTIOBS is the DATE-OBS in PIM-TI (36 bits DHUTI) , format '0xXXXXXX '
 - PIMTIEND is the DATE-END in PIM-TI (36 bits DHUTI), same format than above

- PIMTIREF is the DATE-REF in PIM-TI (36 bits DHUTI) , same format than above
 ???_OBS and ???_END are identical with ???_REF for convenience. ???_REF is
 Reference time from TI sampled during each exposure cycle. This is due to the fact
 that IRC only sample time information once per exposure cycle. Note: PIMTI is the
 primary information directly from telemetry. AFTI- and DATE- are from the timing
 correction based on PIMTI.
- attitude information
 - EQUINOX is the Epoch of Coordinate
 - RA is the Target position at DATE-REF in degrees
 - DEC is the Target position at DATE-REF in degrees
 - ROLL is the Roll Angle at DATE-OBS
 - AA-SOL is the Solar avoidance Angle at DATE-REF in degrees
 - AA-EAR is the Earth avoidance Angle at DATE-REF in degrees
 - AA-LUN is the Lunar avoidance Angle at DATE-REF in degrees
 - TM-SAA is the duration in seconds since last SAA at DATE-REF. Definition of
 SAA is different for different detectors. SAA region is defined by the glitch rate
 map observed by the Star Tracker with arbitrary threshold level. IRC follows this
 threshold. Shifts of 30 and 60 seconds are applied to FIS SW and LW, respectively.
 - SAT-POSX is the Satellite position at DATE-REF in km
 - SAT-POSY is the Satellite position at DATE-REF in km
 - SAT-POSZ is the Satellite position at DATE-REF in km
 - DAYNIGHT is the / Day/night status at DATE-REF These fields are updated as
 pointing analysis goes on from On-board AOCS to G-ADS (Pointing reconstruction
 for Survey mode)
 - STTA-NUM is the number of tracked stars in STT-A at DATE-REF
 - STTB-NUM is the number of tracked stars in STT-B at DATE-REF
 - STTA-MOD is the STT-A Mode status at DATE-REF, either 'TRK', 'ACQ', 'STB',
 'INLR' or 'INLN'
 - STTB-MOD is the STT-B Mode status at DATE-REF, same as above
 - COMMENT: Any strings
 - HISTORY: Any strings

3.2.3 Raw data dimensions

FITS dimension of the NIR frames is 412 (x) × 512 (y) × 2 (short+long exposure sub-frames).

With the AOTZ4, one will obtain 11 or 12 sets of frames:

- 5 sets of pre-dark frame
- 8 or 9 sets of spectroscopy exposure frames
- 1 set of reference imaging exposure frame
- 5 sets set of post-dark frame

The dark frames will be taken, during pre- and post-satellite maneuvering period, with the shutter closed (the filter wheel at so-called "CAL" position).

The spectroscopy frames are taken with dispersers inserted along the optical path, by rotating the filter wheel.

The direct imaging frame is taken with the same ways as for the normal imaging observations (with AOTZ0, Z2, and Z3). The image taken during the spectroscopy mode (AOTZ4) is called as the "reference image". The N3 wide-band filters will be used as the reference images of NIR. Other combinations of the broad-band filters and dispersers are not available.

The satellite starts to maneuver back to the survey mode according to the timer, irrespective of the IRC operation. The last exposure should be discarded since part of the exposure could be made during the maneuver. The present FITS header does not record the status of the satellite attitude control. In the imaging data pipeline the removal of the last exposure is made automatically by checking the source intensity. Such an automatic procedure is not included in the current spectroscopy data reduction software: users need to do it by themselves (see Chapter 6). Note, however, that the automatic removal is not always perfect and users may have to do it manually in some cases even for the imaging data.

3.3 Quick look data

Together with the rawdata, quick look products are distributed in the archive for both imaging and spectroscopy IRC observations. These files are not intended for science and the users are strongly encouraged to run the corresponding pipelines in order to obtain the best out of the raw data.

3.3.1 IRC imaging IRCZ0, IRCZ2 and IRCZ3

As explained in the README file distributed with the data in the archive, the `irc_ql` subdirectory contains, together with a set of log files, a main quick look fits image per detector, with the following naming convention. Its name is `efmslCnDaFVVVxxxxxx_[N]yyy.fits`. The fits prefixes refer to the performed steps during the processing: DARK correction (D), linearity (ln), distortion correction (d) and flatfielding (f). [NSL] refer to each detector. Under the directory of `stacked_IM/` a stacked image of `TARGETNAME_FILTER_EXPOSURE.fits` is also provided. The `irclog` file contains a brief description of each file from the data reduction pipeline. Please consult the README file in the delivery package for more information.

3.3.2 IRC spectroscopy: IRCZ4

The quick look products distributed in the case of spectroscopy observations (IRC04) are the following:

- `TARGETID.SUBID.FILTER_DISPERSER.refimage_bg.fits`: dark, linearity and flatfield corrected reference image.
- `TARGETID.SUBID.FILTER_DISPERSER.specimage_bg.fits`: dark, linearity and flatfield corrected spectroscopy image. This quick look image is usable only for slit-less spectroscopy. For slit spectroscopy further processing with the spectroscopy pipeline is needed.

Auxiliary files are described in the README file distributed in the archive.

3.4 IRCZ4 image orientation and dispersion direction

Since raw NIR images are rotated for technical reasons of data handling in the IRC electronics onboard the satellite, NIR images (NP, NG and N3) will be rotated by 90 deg counterclockwise at the very first stage of the data reduction for convenience in the spectroscopy pipeline.

This is the original orientation in raw images (without rotation for NIR):

- NP: longer wavelength comes at right side (toward positive X).
- NG: longer wavelength comes at left side (toward negative X).

The IRCZ4 data reduction pipeline makes the rotation of the NIR images at the first step. After the NIR rotation, the dispersion directions are the same for all the dispersers in spectroscopy images. Note, however, that NP shows positive dispersions (longer wavelength comes at higher Y), whereas NG shows negative dispersions (longer wavelength comes at lower Y). At the same stage, the orientation of all NIR images is also set right, i.e., the image is neither flipped nor mirrored. Thus one can match the IRC images with other WCS-correct images, such as 2MASS images, only by shifting and/or rotating the images. Since the satellite is designed to scan the sky along the ecliptic latitude on the sky, and the X axis of the IRC array is aligned perpendicular to the scan direction, the Y axis is aligned closely with the ecliptic latitude while the X axis is aligned with the ecliptic longitude.

Chapter 4

IRC Calibration and Accuracy

This chapter offers an overview of the main issues related to the IRC calibration and in-orbit performance. The instrument calibration is addressed in a standard way: dark level, flat-fields, linearity, point spread function, absolute flux calibration and distortion correction. Spectroscopy and imaging are addressed at the same time. Specific topics for each of them are explicitly indicated. Please be aware that the calibration for the phase 3 period has not been completed and the followings are preliminary results.

4.1 Dark image

Five dark images are taken before and after the target observation in a pointing observation for phase 3. The self-dark image is created from these 10 dark frames. This is completely different from the phase 2 observations, where the superdark is used instead of the self-dark for the NIR channel.

4.2 Flatfield

4.2.1 Flatfields for imaging data




Figure 4.2.1: Flatfields for N2, N3, and N4.

The IRC super flats for the NIR bands were derived from all the imaging observations so far taken during the phase 3. Unfortunately, stray light is present and an unexpected high background is seen. This is due to Earth rim light, which is uniform over the Field of View. Therefore, observations of the diffuse background may be severely affected.

The S/N of the superflat is estimated to be 100 for N2 and N3, and about 400 for N4. The superflats will be updated in future.

4.2.2 Flats for spectroscopy images

The spectroscopy flatfields are images made by a large number of blank sky spectroscopy images combined and normalized so that any faint object spectra are removed by clipping averaging techniques. Super-flats are prepared for NP and NG. As will be described at the end of this chapter, these flats show spectral features, which are not due to the sensitivity variation. Therefore object spectra should not follow the 'flat' pattern. However, this 'super-flat' with spectral features is used in the data reduction because the color-term correction actually cancel out the spectral feature correction.

For flat fielding slit spectra, including NG with the point source aperture (Np), the superflats are typical for conventional slit spectroscopy. These flats are also made by combining a large number of blank sky spectra. Preliminary flats are prepared for the Ns and Nh slits. They have low S/N ratios and they could degrade the data quality when applied. Better flats are being prepared.

4.3 Instrument linearity

The detector operation parameters have been adjusted to accommodate the increase of the dark current in phase 3. This reduced the detector well capacity significantly and the saturation level changed from 12000 ADU in phase 2 to 2000 ADU in phase 3. Accordingly the linearity was changed. The data taken with the calibration lamp is used for phase 3 data instead of the laboratory measurement to derive the linearity correction formula. The data taken with constant illumination of the calibration lamp are fitted with a polynomial. The correction accuracy is estimated to be about 5% for the range up to 2000 ADU. Fig. 4.3.2 shows the raw signal (green) and the signal after linearity correction (red) in ADU.




Figure 4.3.2: Raw signals (green) and signals after linearity correction (red) in units of ADU.

4.4 Instrument Point Spread Function

Table 4.4.1 shows the FWHM of the in flight PSF in the imaging mode, based on observations of standard stars, performed in October 2007 after the telescope focus adjustment. It is slightly

degraded from the phase 2 performance due to the degradation of the telescope image quality around 40K (Onaka et al. 2008, Proc. of SPIE, 7010, 70102X).

N2	N3	N4
3.2	3.2	3.2

Table 4.4.1: In orbit PSF (in pixels).

The PSFs are not spherical. Therefore the users are recommended to average individual images in the coadding process, if photometric accuracy is concerned. In some cases, mainly in deep survey, the median filtered image will lose some signal if the images are rotated with respect to each other. To avoid this problem users should use “average” instead of “median filter” when combining individual images.

The PSF in the spectroscopic mode is worse by one or two pixels compared to imaging data. No significant wavelength dependence is seen along dispersers.

4.5 RSRF

Figures 4.5.3 and 4.5.4 show the relative spectral response functions for the NIR filters and dispersion elements. No change has been recognized from phase 2 and the same RSR data can be used for the phase 3 data reduction.




Figure 4.5.3: The Relative Spectral Response Function of the IRC/NIR Camera for F_{λ} .

4.6 Flux calibration for point sources

Observations of the same standard stars employed in phase 2 are being executed. At this stage only tentative absolute calibration results are available.

The raw data were reduced with the IRC imaging pipeline. The pipeline produces one coadded image for each band/exposure configuration, using “median” as the combine mode. Each configuration image corresponds to the exposure unit, listed in Table 4.6.2. The actual




Figure 4.5.4: The Relative Spectral Response Function of the IRC/NIR dispersion elements per photon.

exposure time is the unit number \times the unit exposure time, t_{unit} , which is approximately 0.5844 s.

Table 4.6.2: Exposure time of each band/exposure configuration.

Band	Exposure	unit number*
NIR	short	8
NIR	long	76

*One unit time corresponds to about 0.5844 s.

4.6.1 Estimation of the in-band flux

The in-band flux density of each band at the nominal wavelength, $f_{\lambda}^{\text{quoted}}(\lambda_i)$, was calculated by the following equation:

$$f_{\nu}^{\text{quoted}}(\nu_i) = \frac{\int_{\nu_{is}}^{\nu_{ie}} \frac{R_i(\nu)}{h\nu} f_{\nu}(\nu) d\nu}{\int_{\nu_{is}}^{\nu_{ie}} \left(\frac{\nu_i}{\nu}\right) \frac{R_i(\nu)}{h\nu} d\nu} \quad (4.6.1)$$

or

$$f_{\lambda}^{\text{quoted}}(\lambda_i) = \frac{\int_{\lambda_{is}}^{\lambda_{ie}} R_i(\lambda) \lambda f_{\lambda}(\lambda) d\lambda}{\int_{\lambda_{is}}^{\lambda_{ie}} \left(\frac{\lambda_i}{\lambda}\right) R_i(\lambda) \lambda d\lambda} \quad (4.6.2)$$

where $f_{\lambda}(\lambda)$ is the flux density of a standard star (Cohen template) and $R_i(\lambda)$ is the spectral response (the transmission of the optics and the response of the detector, unit: electron photon⁻¹)

of the band i . Here $f_\nu \propto \nu^{-1}$ or $f_\lambda \propto \lambda^{-1}$ is assumed. The adopted normal wavelengths of each band, λ_i , are listed in Table 4.6.3 along with the range of the integration (λ_{i_s} , λ_{i_e}).

Table 4.6.3: The normal wavelength λ_i and the range of integration, λ_{i_s} and λ_{i_e} .

band	λ_i	λ_{i_s}	λ_{i_e}
N2	2.40	1.60	5.770
N3	3.20	1.60	5.770
N4	4.10	1.60	5.770

4.6.2 Absolute calibration

The conversion factors for phase 3 imaging observations were derived based on observations of standard stars performed until March 2009. The results are summarized in Table 4.6.4. Note that the ratio of the conversion factors between the long and short exposures in the phase is not the one expected from the exposure time. The reason is not known at present. The calibration for phase 3 spectroscopy has not been completed. We simply apply a factor of 0.7 reduction in the sensitivity in the spectroscopy pipeline toolkit at the present.

Table 4.6.4: Conversion factors (ADU exposure⁻¹ to Jy).

Band	short exposure f_s	error (%)	long exposure f_l	error (%)
N2	5.50×10^{-6}	1.85	6.60×10^{-7}	2.16
N3	3.89×10^{-6}	1.96	4.95×10^{-7}	2.37
N4	2.78×10^{-6}	2.13	3.62×10^{-7}	2.28

4.6.3 Stability of the sensitivity

Although the temperature of the IRC is gradually increasing, we do not so far see any systematic change in the sensitivity at the time when this document is being prepared. Updated information on the stability will be posted on the web.

4.7 Flux calibration for extended sources

A correction factor should be applied to convert the point sources flux calibration into extended sources flux. The absolute calibration for diffuse sources is being planned, but is not available at present.

4.8 Color correction

s mentioned in previous section, the quoted values of the IRC flux calibration assume $f_\lambda \propto \lambda^{-1}$. For cases of other incident spectra, the color correction is required.

The quoted value at a reference frequency is given by

$$f_{\nu_i}^{\text{quoted}} = \frac{\int \frac{R_i(\nu)}{h\nu} f_\nu(\nu) d\nu}{\int \left(\frac{\nu_i}{\nu}\right) \frac{R_i(\nu)}{h\nu} d\nu},$$

where R is the response in units of electron per photon. The correction factor K is calculated as

$$f_{\nu_i}^{\text{quoted}} = \frac{\int \frac{R_i(\nu)}{h\nu} f_\nu(\nu) d\nu}{\int \left(\frac{\nu_i}{\nu}\right) \frac{R_i(\nu)}{h\nu} d\nu} = \frac{\int \frac{R_i(\nu)}{h\nu} \frac{f_\nu(\nu)}{f_{\nu_i}^{\text{actual}}} d\nu}{\int \left(\frac{\nu_i}{\nu}\right) \frac{R_i(\nu)}{h\nu} d\nu} f_{\nu_i}^{\text{actual}} = \frac{\int \frac{R_i(\nu)}{h\nu} \frac{f_\nu(\nu)}{f_\nu(\nu_i)} d\nu}{\int \left(\frac{\nu_i}{\nu}\right) \frac{R_i(\nu)}{h\nu} d\nu} f_{\nu_i}^{\text{actual}} \equiv K(\lambda_i) f_{\nu_i}^{\text{actual}}$$

Thus, K is given by

$$K(\lambda_i) \equiv \frac{\int \frac{R_i(\nu)}{\nu} \frac{f_\nu(\nu)}{f_\nu(\nu_i)} d\nu}{\int \left(\frac{\nu_i}{\nu}\right) \frac{R_i(\nu)}{\nu} d\nu}$$

We calculate the correction factors for the following incident spectrum cases:

$$f_\nu(\lambda) = \tau_0 \left(\frac{\lambda}{\lambda_0}\right)^\alpha \left(\frac{2hc}{\lambda^3}\right) \frac{1}{\exp\left(\frac{hc}{\lambda kT}\right) - 1} \quad (4.8.3)$$

with $\alpha = 0, -1, -2$.

The results are shown in the following tables. The reference wavelengths are fixed as: $\lambda_1 = 2.4\mu m$, $\lambda_2 = 3.2\mu m$, and $\lambda_3 = 4.1\mu m$.

Table 4.8.5: Color Correction factors for NIR channel^a – Black Body ($\alpha = 0$)

Intrinsic Temperature (K)	NIR/N2 K(2.4 μ m)	NIR/N3 K(3.2 μ m)	NIR/N4 K(4.1 μ m)
40	–	–	–
50	–	–	–
60	–	–	–
70	–	–	–
80	–	–	–
90	–	–	396.131
100	–	–	164.506
110	–	–	81.786
120	–	873.058	46.429
130	–	297.140	29.139
140	–	121.814	19.760
150	–	58.297	14.242
160	–	31.767	10.776
170	–	19.291	8.482
180	–	12.811	6.895
190	–	9.149	5.756
200	–	6.928	4.914
210	–	5.496	4.275
220	582.603	4.526	3.778
230	316.052	3.839	3.385
240	181.324	3.336	3.069
250	109.374	2.955	2.810
300	16.057	1.952	2.024
350	5.065	1.543	1.643
400	2.631	1.333	1.428
450	1.818	1.212	1.294
500	1.463	1.136	1.204
600	1.167	1.052	1.095
700	1.051	1.012	1.033
800	0.997	0.992	0.994
900	0.970	0.982	0.969
1000	0.957	0.977	0.951
1500	0.963	0.981	0.910
2000	0.990	0.992	0.896
2500	1.013	1.001	0.890
3000	1.031	1.008	0.886
3500	1.045	1.013	0.884
4000	1.056	1.017	0.883
4500	1.064	1.020	0.882
5000	1.071	1.022	0.881
6000	1.081	1.026	0.880
7000	1.088	1.029	0.880
8000	1.094	1.031	0.879
9000	1.098	1.032	0.879
10000	1.101	1.034	0.879
20000	1.116	1.039	0.878
30000	1.121	1.041	0.877
40000	1.123	1.042	0.877
50000	1.125	1.043	0.877
60000	1.126	1.043	0.877

^a Values are calculated for $\lambda_1 = 2.4\mu\text{m}$, $\lambda_2 = 3.2\mu\text{m}$, $\lambda_3 = 4.1\mu\text{m}$.

Table 4.8.6: Color Correction factors for NIR channel^a – Gray Body ($\alpha = -1$)

Intrinsic Temperature (K)	NIR/N2 K(2.4 μ m)	NIR/N3 K(3.2 μ m)	NIR/N4 K(4.1 μ m)
40	–	–	–
50	–	–	–
60	–	–	–
70	–	–	–
80	–	–	938.233
90	–	–	305.576
100	–	–	127.958
110	–	–	64.122
120	–	541.920	36.679
130	–	187.774	23.187
140	–	78.796	15.834
150	–	38.794	11.488
160	–	21.822	8.749
170	–	13.696	6.929
180	–	9.390	5.665
190	–	6.906	4.757
200	–	5.367	4.083
210	546.949	4.356	3.571
220	280.566	3.657	3.172
230	153.521	3.154	2.856
240	89.003	2.779	2.601
250	54.374	2.492	2.393
300	8.881	1.715	1.757
350	3.276	1.390	1.449
400	1.952	1.223	1.276
450	1.477	1.127	1.168
500	1.257	1.069	1.097
600	1.064	1.007	1.011
700	0.989	0.981	0.963
800	0.957	0.971	0.934
900	0.945	0.968	0.915
1000	0.943	0.970	0.902
1500	0.982	0.992	0.875
2000	1.027	1.012	0.868
2500	1.061	1.027	0.866
3000	1.087	1.037	0.865
3500	1.106	1.045	0.865
4000	1.121	1.051	0.865
4500	1.132	1.056	0.865
5000	1.142	1.059	0.865
6000	1.156	1.065	0.866
7000	1.166	1.069	0.866
8000	1.173	1.072	0.866
9000	1.179	1.074	0.866
10000	1.183	1.076	0.867
20000	1.203	1.084	0.868
30000	1.210	1.087	0.868
40000	1.213	1.089	0.868
50000	1.215	1.089	0.868
60000	1.216	1.090	0.868

^a Values are calculated for $\lambda_1 = 2.4\mu m$, $\lambda_2 = 3.2\mu m$, $\lambda_3 = 4.1\mu m$.

Table 4.8.7: Color Correction factors for NIR channel^a – Gray Body ($\alpha = -2$)

Intrinsic Temperature (K)	NIR/N2 K(2.4 μ m)	NIR/N3 K(3.2 μ m)	NIR/N4 K(4.1 μ m)
40	–	–	–
50	–	–	–
60	–	–	–
70	–	–	–
80	–	–	719.020
90	–	–	236.320
100	–	–	99.825
110	–	–	50.445
120	–	339.050	29.088
130	–	120.115	18.531
140	–	51.864	12.748
150	–	26.407	9.316
160	–	15.397	7.143
170	–	10.012	5.694
180	–	7.092	4.686
190	–	5.367	3.959
200	549.483	4.275	3.418
210	264.183	3.541	3.006
220	136.893	3.025	2.685
230	75.855	2.647	2.430
240	44.673	2.361	2.224
250	27.825	2.140	2.055
300	5.291	1.528	1.541
350	2.329	1.268	1.293
400	1.566	1.135	1.154
450	1.270	1.061	1.068
500	1.125	1.017	1.012
600	0.996	0.976	0.946
700	0.949	0.963	0.910
800	0.935	0.962	0.889
900	0.936	0.968	0.876
1000	0.945	0.975	0.868
1500	1.019	1.016	0.855
2000	1.084	1.047	0.855
2500	1.132	1.068	0.857
3000	1.166	1.084	0.860
3500	1.192	1.095	0.862
4000	1.212	1.103	0.864
4500	1.227	1.110	0.866
5000	1.239	1.115	0.867
6000	1.258	1.123	0.869
7000	1.271	1.129	0.871
8000	1.281	1.133	0.873
9000	1.288	1.137	0.874
10000	1.294	1.139	0.874
20000	1.320	1.151	0.879
30000	1.329	1.155	0.880
40000	1.333	1.157	0.881
50000	1.335	1.158	0.881
60000	1.337	1.159	0.881

^a Values are calculated for $\lambda_1 = 2.4\mu\text{m}$, $\lambda_2 = 3.2\mu\text{m}$, $\lambda_3 = 4.1\mu\text{m}$.

4.9 Pixel scale

The pixel scale of the NIR image is determined based on observations of globular clusters and Galactic center with the IRC. In these images we matched the 2MASS coordinates of detected stars with the detector xy coordinates by fitting polynomials and determined the pixel scale. The pipeline software regrid the image with the pixel scale of $1.46''$. The deviation from an ideal grid square are up to 2 pixels at the edge. No appreciable change is noticed from phase 2. Refer to the IRC Data Users's manual for details of the distortion. In summary, the accuracy is about 0.1 pixel (N4 may be slightly worse).

4.10 Astrometry

A corrected and final astrometry can be achieved at the end of the pipeline cross-correlating with the 2MASS catalogue. This option is turned off by default. This is because the software to retrieve the 2MASS catalog may be platform-dependent. To enable this option, "curl" has to be installed in the system. The instructions for it are beyond this manual. Ask your computer administrator for the installation.

The current pipeline has a capability to first include the pointing information from the attitude and orbital control system (AOCS) directly in the WCS format. If matching with the 2MASS data is successful, then the pointing information will be replaced by the matching data. The parameter "WCSROOT" in the FITS header indicates which information (AOCS or 2MASS) is used to determine the coordinates.

4.11 Arrays anomalies

NIR anomalies are shown in Figures 4.11.5 and 4.11.6. Most of them also affects the Spitzer IRAC instrument.

- Muxbleed
- Muxstripes
- Column pulldown
- Banding

4.12 General concerns on slit-less spectroscopy data

This section is dealing mainly with problems related to the slit-less spectroscopy data. Issues for the slit spectroscopy matters are described separately.

- Wavelength reference point: In the slit-less spectroscopy mode, the wavelength reference point depends on the location of objects within the FOV. Therefore, the determination of the source positions on the reference image is very important. Errors in the source positions leads to errors in the assigned wavelengths and, hence the flux calibration.
- Contamination by nearby sources: Spectra of more than two objects aligned along with the Y axis could overlap on the same pixels with different wavelengths. It is impossible to separate the spectral overlap on the observed image, without knowing the spectrum of each object.




Figure 4.11.5: Banding in NIR array

- Contamination by zero-th/2nd order light: For the gratings, images of the zero-th and the 2nd order light can be seen as well as the 1st order image (our prime target for data reduction), although the efficiency for the zero-th and the 2nd order light is very low. All these images contaminate other spectra aligned along with the columns of pixels where the objects exit. These contaminations can be ignored in most cases, and cautions are needed actually only around very bright sources. For the NG spectroscopy with point source aperture (N_p), there is little chance for this kind of contamination to occur since the aperture size is much smaller than the size of the dispersed spectroscopy image along the Y or the dispersion direction.
- Spectral smearing for extended sources: In the slit-less spectroscopy mode, the spectral resolution is determined by the size of the sources (or the PSF structure plus satellite attitude drift). Thus the spectral resolution is lower for extended objects. If an extended object shows resolved structures, the interpretation of the 2D spectra becomes very difficult because of the convolution of the spectrum over the object spatial structure.
- Background spectral features: Although the background sky is essentially "flat" in the imaging mode, it is not true for spectroscopy images.

Note that these features would not be observed with the point source aperture (N_p) and other narrow slits, since the aperture size is much smaller than the size of the dispersed spectroscopy image along the Y or the dispersion direction.

- Faint background areas near the $Y=0$ or $Y=Y_{\max}$ edge of FOV: For the slit area, the background is dominated by the zodiacal light. The spectral-response curve shows a simple pattern with the decreasing sensitivity at the highest and lowest wavelength ends of the disperser's spectral coverage. Thus one will see a background pattern which becomes




Figure 4.11.6: NIR array anomalies: Muxbleed, Muxstripes and column pull-down

faint at the top and bottom of the image in units of ADU. For the slit-less area, both the wavelength and the spatial axis Y go along with the same direction (Y), and thus the observed background image is a spatially convolved background spectrum. Since the length of the spectrum along Y (50-70 pix) is much smaller than the aperture size (256 or 412 pix), the resultant background spectrum is almost constant across Y after being convolved spatially by the large aperture. The regions around $Y=0$ and $Y=Y_{\max}$ are exceptions, where the edge of the aperture prevents full convolution of the background spectrum along the Y direction and, hence, the background signal becomes faint near $Y=0$ and $Y=Y_{\max}$ is seen. Note that this kind of pattern at the very Y edge of the FOV does occur only for the background light, but not for object spectra.

- Jump of the background (ridge) near the center of FOV: Another background feature is a ridge seen near the Y center, stretching along the X axis, seen in grism spectroscopy images. This is caused by the zero-th order light of the grisms. Since the zero-th order light image forms at an offset position from the reference image, only about a half of the FOV suffers from its contamination.

- Satellite attitude stability/instability: Position shifts among sub-frames are frequently observed due to the satellite attitude drift in the pointing attitude control mode. The drift is as large as several pixels in the worst cases. To correct the drift, one needs to register images among spectroscopy sub-frames and between spectroscopy and reference images. The second correction is very important to determine the wavelength reference point. Note that it takes about 30 sec to switch the spectroscopy mode to/from the imaging mode for the filter wheel rotation. Thus the time interval between the last spectroscopy sub-frame and the first imaging sub-frame is longer by this period than the interval between taking spectroscopy sub-frames. To measure the image drift among spectroscopy images, we use cross-correlation image matching technique. To measure the image drift between spectroscopy and reference images, we could use the same cross-correlation technique. In this cross-correlation we use a template spectrum that was extracted from the data with negligible drifts. Then by comparing the template with spectra extracted from the spectroscopy data in question, we estimate the relative drift.

For spectra of diffuse sources at the narrow slits (N_h , and N_s), we do not have to take account of the satellite attitude stability, if the size of the drift is much smaller than that of the objects.

- Ghosts in N_p observations: Ghosts relating the N_p slit have also been recognized. Left panel of Fig 4.12.7 shows an example of the imaging data. There are sources seen on the slit mask region, which must be ghosts from the sources in the N_p slit. Right panel of Fig 4.12.7 shows the corresponding spectral data, in which ghost spectra overlap with the source spectrum. No definite origin for these ghosts has been elucidated and thus no clear recipe has been prepared to correct for them at present.




Figure 4.12.7: Ghosts generated in N_p observations. Left panel: Imaging data. Right panel: spectroscopic data

Chapter 5

Imaging toolkit cookbook

5.1 Introduction

The IRC imaging data reduction toolkit is developed to address and correct any IRC Instrument features, such as linearity, flat fielding, distortion etc., and converts the raw ADU signal to physically meaningful units (i.e. flux). However, in the current version, the data number of resultant image is ADU per frame, and they should be multiplied by a certain constant to convert it to a physical unit such as Jy. We will provide a table of the conversion of ADU/s to Jy for point sources in addition to the integration time for each frame. The in-orbit calibration is made based on aperture photometry with an aperture radius of 10 pixels for the NIR. For other aperture sizes, observers have to make an aperture correction, which is currently not known owing to the unknown PSF (not stable and not well defined). Similar to the Spitzer IRAC arrays, reflection of the light within the arrays exists also for the IRC arrays. The calibration for the diffuse light is currently not available.

The toolkit (including the entire source code) will be released, and be progressively updated reflecting the user's feedback. The user will receive the raw data plus automatic toolkit (to make basic science data). The user may customize the toolkit at his/her own risk.

We provide super-flats, which will be updated periodically with the version number. e.g., Super-darkYYMMDD.fits

The toolkit for phase 3 data reduction is released separately from that for phase 2 data reduction. The user interface is basically the same, but users should not use it for phase 2 data reduction. It can be installed simultaneously with that for the phase 2 data reduction toolkit as described below. For users who are familiar with the phase 2 data reduction, the usage of the toolkit is completely the same although the treatment of dark frames and the linearity correction are different.

5.2 General overview of the toolkit processing

The toolkit runs on IRAF, and it consists of two main steps plus an optional step.

At present the toolkit concept consists of 3 "boxes" currently in a state of development.

- pre-pipeline processor (*Red-Box*):
- pipeline processor (*Green-Box*):
- post-pipeline processor (*Blue-Box*):

- Pre-pipeline Processor (Red Box) : Produces *Basic Data*
 - redbox.ircslice: header formatting, slice IRC 3D images into usual 2D ones
 - redbox.mkirclog: making the observing log file “irclog”
- Pipeline (Green Box) : Produces *Basic Science (Calibrated) Data*
 - greenbox.anomalous_pix: mask Bad/Dead pixels
 - greenbox.wraparound: wrap around correction
 - greenbox.dark: subtract dark current
 - greenbox.ircnorm: Normalize sampling and compression bit shift
 - greenbox.scatt_light: Subtract scattered light pattern
 - greenbox.cosmic_ray: remove cosmic rays
 - greenbox.linearity: correct linearity of the detector response
 - greenbox.saturation: mask saturated pixels
 - greenbox.slit_mask: mask slit area on detector
 - greenbox.flat: flatten the pixels
 - greenbox.aspect_ratio: Distortion Correction (Aspect ratio resampling)
- Post-Pipeline Processor (Blue Box) (This is a separated package, but called from pipeline processor by default)
 - bluebox.coadd: to form a co-added image
 - * source_extract: Perform source extraction
 - * calcshift: Calculate shift&rotation between images
 - * adjust_sky: adjust sky level before stacking
 - * irc_stack: stack individual frames to form a co-added image

The pipeline can be run automatically or interactively step by step.

5.3 Expected Data Processing Rate (minimum expectation)

$$\text{NIR} = 412 \times 512 [\text{pixels}] * 16 [\text{bit/pixel}] / 8 [\text{bit/byte}] = 412 \text{ Kbyte/frame}$$

- 1 NIR fits = 412 Kbyte/frame * 2 frame/fits = 824 Kbyte/fits file
- AOTZ0: 6 exposure cycles/pointing * (1 NIR fits)/exposure cycle ~ 10.8 Mbyte/pointing
- AOTZ2: 6 exposure cycles/pointing * (1 NIR fits)/exposure cycle ~ 10.8 Mbyte/pointing
- AOTZ3: 6 exposure cycles/pointing * (1 NIR fits)/exposure cycle ~ 10.8 Mbyte/pointing

The toolkit requires 3 or 4 times of disk space compared to the data.

5.4 How to install the IRC imaging Toolkit

5.4.1 Requirements

The toolkit is developed in a Linux PC environment and has also been successfully run in the OSX Unix environment. The toolkit requires the following environment for its full function:

- unix (Solaris, MacOS X, Linux, BSD)
- IRAF 2.12.2a or later
- gcc 3.0 or later
- perl
- curl (for WCS calculation on Solaris machines)

We notice that the toolkit does not work properly under IRAF 2.14 and it is not fully tested with later versions of IRAF 2.14.

5.4.2 Install IRAF

- <http://iraf.noao.edu/>

5.4.3 Download IRC imaging data reduction software package

The latest version of the toolkit with installation and operating instructions for the phase 3 data reduction can be obtained from the AKARI Observer's web site (see section 1.2). It can be installed simultaneously with that for the phase 2 data reduction toolkit, but must be installed in a different directory.

5.4.4 Unpack `irc_p3.tgz`

- `mv ircYYMMDD.tgz /where/you/install/irc_p3`
- `cd /where/install/irc_p3`
- `tar xvzf ircYYMMDD_p3.tgz`

5.4.5 Make `irc` binaries

- `cd /where/you/install/irc_p3/src`
- `make`

This will create binary files in `/where/you/want/to/install/irc/bin/`

5.4.6 Run `"setpath.pl"`

- `cd /where/you/install/irc_p3/lib`
- `perl setpath.pl`

This will rewrite the `"setpath.dat"`. Please check the following line in `"setpath.dat"` is the following format

set irchome = `"/where/you/install/irc_p3/"`

This line should indicate the location where you installed the `irc_p3` package.

5.4.7 Perl path

Typing **which perl** in the unix environment indicates where the perl is installed in your system. The toolkit assumes that the perl is installed in `/usr/local/bin/perl`

Therefore, those who have the perl binary elsewhere, should do as follows:

- If you know the root password, please create a symbolic link in `/usr/local/bin` by typing:
 - `cd /usr/local/bin`
 - `ln -s 'which perl' perl`

It will create a symbolic link **perl** in `/usr/local/bin`.

- If you do not know the root password, please modify the first line of every perl script file in `/where/you/want/to/install/irc/perl`. For example, if you have perl in `/usr/bin/perl`, please modify it as;
 - `#!/usr/local/bin/perl`
 - `-->`
 - `#!/usr/bin/perl`

As long as you have perl in `/usr/bin/perl`, you can also achieve the same result by running a script

- `cd /where/you/want/to/install/irc/perl`
- `perlpath.sh`

which will create a directory **temp** containing perl files whose first lines are modified as above. Then you can overwrite these new perl files by typing;

- `mv ./temp/*.pl .`

Those who do not have perl in `/usr/bin/perl`, please modify **perlpath.sh** and indicate the location of your perl.

5.4.8 Add IRC_P3 entry to IRAF

- If you know root password and you installed IRAF package into for example `/iraf`,
 - `cd /iraf/iraf/unix/hlib/`
 - edit the file `extern.pkg`

Please add the following 2 lines to `A /iraf/iraf/unix/hlib/extern.pkg`,

reset irc_p3 = /where/you/install/irc_p3/

task \$irc_p3.pkg = irc_p3\$irc_p3.cl

DO NOT FORGET THE "\$" BEFORE THE IRC_P3.PKG!! DO NOT FORGET THE LAST SLASH!!

- If you do not know the root password then you should launch iraf from your home directory every time you want to use the `irc_p3` package.
 - `cd` (change directory to your home directory)
 - `mkiraf` (only when using IRAF for the very first time)

This will create the "login.cl" file in your home directory. Then edit "login.cl" and add 2 lines:

```
reset irc_p3 = /where/you/install/irc_p3/
```

```
task $irc_p3.pkg = irc_p3$irc_p3.cl
```

DO NOT FORGET THE "\$" BEFORE THE IRC_P3.PKG!! DO NOT FORGET THE LAST SLASH!!

the toolkit is now installed and is ready to be run !!

5.5 How to UPGRADE the version of IRC_P3 imaging toolkit

Upgrades to the IRC imaging toolkit is a progressive and ongoing process and new versions of the toolkit will be available to users throughout the course of the mission. On receiving a new version of toolkit package (e.g., irc_p3YYMMDD.tgz), the following commands are required to be input;

- mv irc_p3YYMMDD.tgz /where/you/installed/previous/version/
- cd /where/you/installed/previous/version/
- tar xvzf irc_p3YYMMDD.tgz

These commands will **OVERWRITE** any old files/directories. Then, follow the original procedure described in 5.4.5 and 5.4.7. Finally, please type following commands when you use a new version of the toolkit for the first time.

- launch IRAF
- load the irc_p3package by typing "irc_p3"
- type "unlearn_all"
- load the irc_tool package by typing "irc_tool"

5.6 Setting up your toolkit environment and running the pipeline

The steps to reduce the raw data are outlined below.

5.6.1 Creating the directory structure

The toolkit assumes the following directory structure (see Fig.5.6.1);


```
~/anyname +
——rawdata (must be this name)
——anyname (your working directory)
```

e.g.

```
~/data/rawdata/
```

```
~/data/working/
```

The toolkit should be run in the working directory. Thus you may create sets of these directory structures for different sets of IRC data.



```


xterm
polaire:yita % pwd
/home/yita
polaire:yita % tar xzf sample_data.tgz
polaire:yita % cd sample_data
polaire:yita % mkdir yita
polaire:yita % ls
rawdata/ yita/
polaire:yita % █

```

Figure 5.6.1: Example directory structure for IRC toolkit.

5.6.2 Launch IRAF

Launch IRAF in your home directory and check that you have an entry for the `irc_p3` package in the list of the IRAF packages. If you install both the toolkits for phase 2 and phase3, both `irc` and `irc_p3` should appear in the list of the IRAF packages (see Fig.5.6.2).



```

xterm
NOAO PC-IRAF Revision 2.12.2a-EXPORT Wed Jul 14 20:45:34 MST 2004
This is the EXPORT version of PC-IRAF V2.12 supporting most PC systems.

Welcome to IRAF. To list the available commands, type ? or ??. To get
detailed information about a command, type 'help command'. To run a
command or load a package, type its name. Type 'bye' to exit a
package, or 'logout' to get out of the CL. Type 'news' to find out
what is new in the version of the system you are using. The following
commands or packages are currently defined:

  dataio.    irc.      lists.     plot.      stsdas.    utilities.
  dbms.      irc_p3.   noao.     proto.     system.    xdimsum.
  images.    language. obsolete.  softtools. tables.

c1> █

```

Here

Figure 5.6.2: Start up screen for IRAF showing the IRC package visible in the list of IRAF packages.

Then you can move to your working directory before starting to run the different tools by typing:

- `cd to_your_working_directory`

where `to_your_working_directory` should follow the rules explained in Section 5.6.1.

5.6.3 Load the IRC_P3 package

The `irc_p3` package can be loaded by typing “`irc_p3`”. You should then see the IRC pipeline splash screen (welcome message) and a list of the available IRC packages (see Fig.5.6.3). The

screen shows the version of toolkit, super-flat, super-dark, linearity, and distortion. Please let us know these numbers if you send any email to the help desk iris_help@ir.isas.jaxa.jp to inquire any trouble with the toolkit.

```
xterm
dataio.  irc.    lists.  plot.   stsdas. utilities.
dbms.   irc_p3. noao.   proto.  system.  xdimsum.
images.  language. obsolete. softtools. tables.
c1> irc_p3
+-----+
|                                     |
| AKARI IRC imaging data reduction pipeline |
| pipeline version: 080924P3             |
| flat version: 080925P3                |
| linearity version: 080924P3           |
|                                     |
| ###This version is only for Phase-3 data### |
|                                     |
| Copyright (C) 2005                     |
| Institute of Space and Astronautical Science, |
| Japan Aerospace Exploration Agency         |
|                                     |
| For help, send emails to iris_help@ir.isas.jaxa.jp |
|                                     |
+-----+
bluebox.  irc_tool.  prepipeline  unlearn_all
greenbox. pipeline  redbox.
ir>
```

Figure 5.6.3: Start up screen for the IRC package showing the available modules and tools. The start up splash screen gives the current version of the toolkit, and current versions of flat, dark, linearity, distortion files etc.

5.7 The pre-pipeline processor (Red-Box)

Note that prepipeline processor is a one-time-only process. Do not run prepipeline twice.

5.7.1 Configuration

Before running prepipeline, you can configure the parameter for prepipeline by typing “epar prepipeline”. This displays the parameter screen shown in Figure 5.7.4




Figure 5.7.4: parameter screen for the Red-Box showing the available parameters.

Please do not change the parameter “irccons”. Prepipeline has only one changeable parameter, “verbose”. If you want to see verbose progress messages, change it to “yes”. The default is “no”.

5.7.2 Running the prepipeline processor

The prepipeline processor consists of two functions.

- redbox.ircslice: slice IRC 3D images into usual 2D ones
- redbox.mkirclog: making the observing log file “irclog”

The prepipeline processor is run by entering “prepipeline” at the IRAF command prompt. Alternatively, the individual Red-Box modules can be run by entering “redbox” at the IRAF command prompt. The present configuration of the pre-pipeline modules is shown in Fig 5.7.5:




Figure 5.7.5: Present configuration of the Red-Box pre-pipeline modules.

along with the current flat, dark, distortion, and linearization versions, e.g. ;

1. **redbox.ircslice**

The number of FITS files produced for any given single pointing will depend on the AOT. Each AOT comprises of a combination of exposure cycles (EC), Filter Wheel changes (W) and Dither Maneuvers (M) (see Fig.2.2.4). The IRC FITS data is not a usual 2D one. A raw data FITS file is created for each Exposure Cycle during a pointing for the NIR channel. The filename format is given as F*****_N.fits, where ***** is a distinct incremental reference number. A NIR raw fits data file is a data cube containing 2 frames within it, corresponding to one short and one long exposure.

In addition to the Exposure Cycles, 5 Dark frames are taken at the beginning and the end of the operation (i.e. extra 10 FITS files). Therefore, as shown in Figure 2.2.4 for AOT IRCZ2, for a single pointing, the maximum number of raw data files will comprise of $(1 \text{ NIR}/\text{EC} \times 7 (\text{EC}) + 10(\text{Dark}) = 17$ FITS files for one pointing. Consequently, for AOT IRCZ3, for a single pointing, the raw data files will comprise of $(1 \text{ NIR})/\text{EC} \times 8(\text{EC}) + 10(\text{Dark}) = 18$ FITS files for one pointing. In addition to the raw FITS files, a text file is also included giving details of the original target list for the observation.

The "redbox.ircslice" module slices each raw FITS file into the individual frames (separates all individual IRC frames for one Exposure Cycle). Thus for every NIR raw FITS file (including the Dark), redbox.ircslice will create 2 FITS files (corresponding to the short and long exposure). Therefore after running "redbox.ircslice" on a single pointing for AOT IRCZ3 you can expect as many as 50 individual FITS files. The filename format takes the original format with an extension defining the channel (N) and frame number (001-002).

Fig. 5.7.7 shows the images of IRC raw data for the NIR bands. The orientation of the images are such that the NIR is rotated by 90 degrees. Please note the dark areas in each images. These areas are reserved for slit-spectroscopy, and they are supposed not to receive any light. Therefore, these regions are useful to monitor the dark level. Hereafter, we refer to this this dark area as the "slit area" and the other as the "imaging area".

2. **redbox.mkirclog**

The "redbox.mkirclog" creates the observing log file "irclog". This is a text file, with content shown in Table 5.8.1. The contents of the irclog file summarize the nature of the processed files in the working directory. The table entries correspond;

- FRAME: The filename corresponding to the "sliced frame" (e.g. following the format such as F23340_N001.fits as described above)
- OBJECT: Target name taken from the original target list
- NAXIS: Number of pixels in cross-scan direction (256 for MIR and 412 for NIR)
- FILTER: Filter name (i.e. N2,N3,N4 or DARK)
- RA-SET: Right ascension coordinates
- DEC-SET: Declination coordinates
- AOT: AOT type (e.g. IRCZ2, IRCZ3 etc) item EXPID: Sequential frame number during an exposure cycle (1 or 2)
- IDNUM: Pointing ID
- SUBID: sub-Pointing ID (greater than 1 for multi-pointing observations)




Figure 5.7.6: IRC/NIR raw FITS file data structure.




Figure 5.7.7: Image of NIR raw data. The NIR raw FITS file is 2 frame deep (corresponding to 1 short and 1 long exposure).

5.8 Before running the pipeline processor

After running "prepipeline", you will get 2 text files, namely "irclog" and "darklist.before".

- irclog

The irclog file is used to select the data to be reduced and any unnecessary entries should be removed from the irclog file, editing it by hand. Alternatively entries and unnecessary lines can be commented out by adding # to the head of the entries.

NOTE: the DARK frames and any grism/prism images need to be removed/commented-out before running the "Green-Box" pipeline. **This is automatically done by prepipeline.**

In general, bad frames may cause a failure in the pipeline at a later stage downstream, the best strategy may be an iterative run where, if a crash occurs, the individual frames can be examined and the culprits excluded from future runs of the Green-Box. The data frame taken during the maneuver can be also automatically discarded, so you need not examine each frame and edit irclog.

- darklist.before

In a pointing observation, 5 dark frames are taken at the beginning and the end of the operation in the phase 3. In the phase 3 data reduction, the self-dark created from these dark frames is always used to estimate the dark current.


Table 5.8.1: Sample of the irclog file

FRAME	OBJECT	NAXIS1	FILTER	RA-SET	DEC-SET	AOT	EXPID	IDNUM	SUBID
#F011131797_N001	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	1	1900359	1
#F011131797_N002	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	2	1900359	1
#F011131798_N001	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	1	1900359	1
#F011131798_N002	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	2	1900359	1
#F011131799_N001	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	1	1900359	1
#F011131799_N002	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	2	1900359	1
#F011131800_N001	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	1	1900359	1
#F011131800_N002	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	2	1900359	1
#F011131801_N001	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	1	1900359	1
#F011131801_N002	"LMC_P3_2C135"	412	DARK	82.75252	-65.88891	IRCZ2	2	1900359	1
#F011131802_N001	"LMC_P3_2C135"	412	NP	82.75252	-65.88891	IRCZ2	1	1900359	1
#F011131802_N002	"LMC_P3_2C135"	412	NP	82.75252	-65.88891	IRCZ2	2	1900359	1
F011131803_N001	"LMC_P3_2C135"	412	N3	82.75252	-65.88891	IRCZ2	1	1900359	1
F011131803_N002	"LMC_P3_2C135"	412	N3	82.75252	-65.88891	IRCZ2	2	1900359	1
F011131804_N001	"LMC_P3_2C135"	412	N3	82.75364	-65.8848	IRCZ2	1	1900359	1
F011131804_N002	"LMC_P3_2C135"	412	N3	82.75364	-65.8848	IRCZ2	2	1900359	1
#F011131805_N001	"LMC_P3_2C135"	412	NP	82.75364	-65.8848	IRCZ2	1	1900359	1
#F011131805_N002	"LMC_P3_2C135"	412	NP	82.75364	-65.8848	IRCZ2	2	1900359	1
#F011131806_N001	"LMC_P3_2C135"	412	NP	82.74459	-65.88335	IRCZ2	1	1900359	1
#F011131806_N002	"LMC_P3_2C135"	412	NP	82.74459	-65.88335	IRCZ2	2	1900359	1
F011131807_N001	"LMC_P3_2C135"	412	N3	82.74459	-65.88335	IRCZ2	1	1900359	1
F011131807_N002	"LMC_P3_2C135"	412	N3	82.74459	-65.88335	IRCZ2	2	1900359	1
F011131808_N001	"LMC_P3_2C135"	412	N3	82.73914	-65.88638	IRCZ2	1	1900359	1
F011131808_N002	"LMC_P3_2C135"	412	N3	82.73914	-65.88638	IRCZ2	2	1900359	1
#F011131809_N001	"LMC_P3_2C135"	412	NP	82.73914	-65.88638	IRCZ2	1	1900359	1
#F011131809_N002	"LMC_P3_2C135"	412	NP	82.73914	-65.88638	IRCZ2	2	1900359	1
#F011131810_N001	"LMC_P3_2C135"	412	DARK	39.74704	-48.87008	IRCZ2	1	1900359	1
#F011131810_N002	"LMC_P3_2C135"	412	DARK	39.74704	-48.87008	IRCZ2	2	1900359	1
#F011131811_N001	"LMC_P3_2C135"	412	DARK	34.73183	-43.88028	IRCZ2	1	1900359	1
#F011131811_N002	"LMC_P3_2C135"	412	DARK	34.73183	-43.88028	IRCZ2	2	1900359	1
#F011131812_N001	"LMC_P3_2C135"	412	DARK	31.62331	-40.16951	IRCZ2	1	1900359	1
#F011131812_N002	"LMC_P3_2C135"	412	DARK	31.62331	-40.16951	IRCZ2	2	1900359	1
#F011131813_N001	"LMC_P3_2C135"	412	DARK	28.98775	-36.5962	IRCZ2	1	1900359	1
#F011131813_N002	"LMC_P3_2C135"	412	DARK	28.98775	-36.5962	IRCZ2	2	1900359	1
#F011131814_N001	"LMC_P3_2C135"	412	DARK	26.45258	-32.7553	IRCZ2	1	1900359	1
#F011131814_N002	"LMC_P3_2C135"	412	DARK	26.45258	-32.7553	IRCZ2	2	1900359	1
#F011131815_N001	"LMC_P3_2C135"	412	DARK	24.12861	-28.86755	IRCZ2	1	1900359	1
#F011131815_N002	"LMC_P3_2C135"	412	DARK	24.12861	-28.86755	IRCZ2	2	1900359	1

5.9 The pipeline processor (Green-Box)

5.9.1 Configuration

Before running the pipeline, you can configure the parameters for the pipeline by typing “epar pipeline”



```

xterm
  IRAF
  Image Reduction and Analysis Facility
PACKAGE = irc_p3,
  TASK = pipeline

(irccons=  constants.database) IRC constants database file name
(com_mod=          median) combine mode: average/median
(sky_are=         1) sky matching area: 1:common area 2:whole area
(det_sig=         3.) Threshold in sigma for source detection
(sig_rej=         3.) Rejection unit in sigmas
(max_itr=         10) Maximum number of iterations
(obslog =         irclog) output of the mkirclog
(cosmicr=         yes) Detect and replace cosmic rays?
(wcs =           yes) Try to compute wcs and write it in the header?
(coaddsh=        no) Coadd short exposure frames?
(interac=        no) Run pipeline interactively?
(deltemp=        yes) Delete intermediate files?
(rejecti=        avsigclip) rej in coadd:minmax|ccdclip|crreject|sigclip|lavs
(rej_sky=        yes) Remove image(s) with outlier sky level?
(submeds=        no) Subtract median filtered sky in adjust_sky?
(coadd =         yes) Coadd?
(default=        yes) Use pipeline's default flat?
More
ESC-? For HELP

```

Figure 5.9.8: Screen for parameter configuration for pipeline.

The pipeline has several parameters.

- `irccons` (string, default=`constants.database`):
NEVER CHANGE THIS. This is the irc constant file name.
- `com_mod` (string, average/median, default=`"median"`):
 Method of combination of frame images.
 - average:
 - median:
- `com_area` (int, 1 or 2, default=`2`):
 Coadded image area of stacked frames used for extraction (see Fig. 5.9.9, **NOTE:** although strictly speaking a Blue-Box process but is run from the Green-Box Pipeline script).
 - **THIS PARAMETER IS NOT SUPPORTED YET, AND YOU WILL GET THE WHOLE AREA IMAGE EVEN IF YOU CHOOSE 1 TO GET THE COMMON AREA.**
 - 1: Only the common area (red region) is extracted.
 - 2: The whole area (areas within green dashed line) is extracted.
- `sky_are` (int, 1 or 2, default=`2`):
 Area of sky to be used for statistics to adjust sky level before coadding frames.

- 1: Only the common area is used.
- 2: The whole area is used.
- `det_sig` (real, min=1.0, max=1000.0, default=4.0):
Source detection threshold in sigmas.
- `sig_rej` (real, min=0.0, max=100.0, default=3.0):
Rejection unit in sigmas.
- `max_itr` (int, min=1, max=10, default=10):
Maximum number of iterations in statistical process.
- `obslog` (string, default=irclog):
NEVER CHANGE THIS. Output filename of redbox.mkirclog
- `wcs` (boolean, yes or no, default=no):
Try to match the 2MASS sources to calculate wcs? To use this function, you should have internet connection to automatically download 2mass catalog from the internet. This process will not be executed as default. Note; although the toolkit was checked on Solaris machines also. **Solaris does not have curl in the original applications. You need to install it to run WCS.**
- `selfdar` (boolean, yes or no, default=no):
Use an alternative dark to the super-dark provided?
- `coaddsh` (boolean, yes or no, default=no):
Coadd short exposure frames as well as long ones?
- `interac` (boolean, yes or no, default=no):
option to run pipeline interactively
With this option selected, the pipeline can be run step by step, e.g. as
`Greenbox.anomalous_pix`
`Greenbox.dark`, etc
or alternatively by typing `Greenbox` then running from inside the Green-Box as
`anomalous_pix`
`dark`, etc.
- `deltemp` (boolean, yes or no, default=yes):
delete any temporary created files?
- `rejecti` (string, none||minmax||ccdclip||crreject||sigclip||avsigclip||pclip, default=sigclip):
Type of rejection operation performed in coadding.
 - none : No rejection
 - minmax : Reject the nlow and nhigh pixels
 - ccdclip : Reject pixels using CCD noise parameters
 - crreject : Reject only positive pixels using CCD noise parameters
 - sigclip : Reject pixels using a sigma clipping algorithm
 - avsigclip : Reject pixels using an averaged sigma clipping algorithm
 - pclip : Reject pixels using sigma based on percentiles

- `rej_sky` (boolean, yes or no, default=yes):
activate if you want to reject any images which have outlier sky level from the coaddition process. Some frames may be taken during maneuver, and the pipeline will detect such frames by watching their sky level.
- `submeds` (boolean, yes or no, default=no):
activate if you want to make a median filtered sky image and subtract it from each image before coadding. This option is useful for deep-imaging observation where the sky has no structure.
- `coadd` (boolean, yes or no, default=yes):
de-activate if you do not want to try to coadd images. This option is useful for users who have their own coaddition strategy and software.
- `default` (boolean, yes or no, default=yes):
This parameter defines which flat is used in the toolkit. De-activate if you want to use your own flat images instead of using the toolkit-default flats. In that case, you have to prepare flat images for three filters (N2,N3,and N4) and put them in `/where/you/installed/irc/lib/flat/user/`. Their file names should be named as those of the flat images in `/where/you/installed/irc/lib/flat/soramamari/`.
- `verbose` (boolean, yes or no, default=no):
activate if you want to print verbose progress messages




Figure 5.9.9: Area utilized for the Co-added images depends upon the parameter `com_area`. The 2 options are common area (red region) and whole area (within green dashed region)

5.9.2 Running Green-Box pipeline module

The Green-Box pipeline processor can be run by entering "pipeline" at the IRAF command prompt. The Green-Box pipeline produces the basic calibrated data and currently consists of the following steps

- `greenbox.anomalous_pix`: Mask Bad/Dead pixels
- `greenbox.dark`: Subtract dark current
- `greenbox.ircnorm`: Normalization for sampling and data compression

- `greenbox.cosmic_ray`: Detect and replace cosmic rays in MIR images.
- `greenbox.linearity`: Correct linearity of the detector response
- `greenbox.saturation`: Mask saturated pixels
- `greenbox.slit_mask`: Masks the slit area of IRC field of view
- `greenbox.flat`: Flatten the pixels
- `greenbox.aspect_ratio`: Distortion Correction (Aspect ratio resampling)

Alternatively, the individual Green-Box modules can be run interactively by 3 possible methods;

1. By setting the `interac` parameter in the parameter list
2. By running the pipeline with the command `pipeline interactive=yes`
3. By running the pipeline with the command `pipeline interactive+`

When running the pipeline interactively, individual steps may be entered as

`Greenbox.anomalous_pix`

`Greenbox.dark`, etc

or alternatively by typing `Greenbox` then running from inside the Green-Box as

`anomalous_pix`

`dark`, etc

When running interactively, there are options to perform/skip/stop each process. The present configuration of the Green-Box pipeline modules are shown in Fig 5.9.10:

Starting from the original input FITS file (e.g. `F23342_N004.fits`). At each step of the Green-Box pipeline processing a qualifier is added as a prefix to the original filename (note the original FITS files are preserved). These prefixes build up over each processing step. The prefixes are summarized in Table 5.9.2.

1. Mask bad or dead pixels: (`greenbox.anomalous_pix`)

Bad or dead pixels were identified by using pre-flight laboratory data. Mask files are stored in `ircroot/lib/anomalous_pix`. They are shown in Fig. 5.9.11. After masking bad/hot pixels, an "a" will be added as a prefix to the original filename such that `F23342_S004.fits` becomes `aF23342_N004.fits`.

2. Dark Subtraction (`greenbox.dark`)

In a pointing observation, 5 dark frames are taken at the beginning (pre-dark) and the end of the operation. In phase 3 data reduction, the selfdark data created from these dark frames are always used because of the increase of the dark current and the number of hot pixels.

Due to various reasons (1st frame effect, and so on), the dark level may vary during a pointing. Therefore we monitor the slit-area as a reference of the dark level, and we **shift** the self-dark by adding/subtraction a constant to them and then subtracting this from each image to account for the changes in the dark level.

After the dark subtraction, a "D" will be added such that `aF23342_N004.fits` becomes `DaF23342_N004.fits`




Figure 5.9.10: Present configuration of the Green-Box pipeline modules.



Figure 5.9.11: Mask file. Outlier pixels have a value of 0 (white) and others 1 (black). Any outlier pixels will be masked out by mutipling the mask file to images of concern.

3. Normalization: (greenbox.ircnorm)

To reduce the readout noise of the detectors the IRC data is read with the Fowler sampling method (non-destructively reading and summing the array multiple times (determined by the Fowler number) then dividing this resulting sum by the Fowler number. However, when the data is transmitted to the ground, for the purpose of data compression, the least significant bit is dropped. The normalization process accounts for this bit loss by correcting the data value by

$$A_{\text{corrected}} = \frac{A_{\text{uncorrected}} * 2^{\text{bitshift}}}{\text{Fowler number}} \quad (5.9.1)$$

Where the *bitshift* represents the number of bit shifts employed.

After the normalization process a "n" will be added such that `DwaF23342_N004.fits` becomes `nDwaF23342_N004.fits`

`nDaF23342_S004.fits` becomes `cnDaF23342_S004.fits`

4. linearity correction: (greenbox.linearity)

The linearity correction is made as explained in section 4.3.

After the linearity correction, a "l" will be added such that `CnDaF23342_N004.fits` becomes `lCnDaF23342_N004.fits`.

5. Saturation: (greenbox.saturation)

Any pixels that are marked as saturated are masked. Physical detector saturation occurs around 2000 ADU (after ircnorm) for the NIR detector in the phase 3. Therefore, any pixels with values greater than the "scaled values" in the short exposure frame are picked out and the corresponding pixels in the long exposure frames will be masked out to be 0. The "scaled values" in the exposure frames are calculated by

$$S_{\text{short exposure in ADU}} = S_{\text{physical saturation in ADU}} * \frac{\text{Exposure Time}_{\text{short frame}}}{\text{Exposure Time}_{\text{long frame}}} \quad (5.9.2)$$

This is done because the IRC uses Correlated Double Sampling and with the current IRC operating clock, we cannot tell which pixels are saturated by long exposure frames alone.

After masking saturated pixels, a "s" will be added such that `lCnDaF23342_N004.fits` becomes `slCnDaF23342_N004.fits`

Table 5.9.2: Prefixes added during Green-Box Pipeline Processing

Prefix	module	action
a	greenbox.anomalous_pix	Mask Bad or Dead Pixels
D	greenbox.dark	Dark Subtraction
n	greenbox.norm	Normalization
C	greenbox.cosmic_ray	Detect and Replace Cosmic Rays
l	greenbox.linearity	Linearity Correction
s	greenbox.saturation	Mask Saturated Pixels
m	greenbox.slit_mask	Slit Mask
f	greenbox.flat	Flat Fielding
e	greenbox.aspect_ratio	Aspect Ratio Resampling

6. Slit Mask: (greenbox.slit_mask)

The slit mask processing masks the slit area in the IRC Field of View.

After the slit mask processing, a "m" will be added such that `s1CnDaF23342_S004.fits` becomes `ms1CnDaF23342_N004.fits`

7. Flat Fielding: (greenbox.flat)

The flat fielding is made using the imaging super flats, described in section 4.2. In the near future, we plan to attach the most suitable flat images to every distributed data set. These flats can then be selected by putting them in `/where/you/installed/irc/lib/flat/user` and deactivating the "default_flat" parameter.

After the flat fielding process, a "f" will be added such that `ms1CnDaF23342_N004.fits` becomes `fms1CnDaF23342_N004.fits`

8. Aspect ratio resampling: (greenbox.aspect_ratio)

This is a distortion correction. The module corrects aspect ratios of pixels to be square i.e. Aspect ratio is corrected to 1 to 1 by resampling the image. Thus the toolkit corrects the linear distortion only. Non-linear distortion is not corrected for at present since it is assumed to be negligible.

After the resampling, a "e" will be added such that `fms1CnDaF23342_N004.fits` becomes `efms1CnDaF23342_N004.fits`

Therefore at the end of the Green-Box, correctly processed frame files should have a `efmslCcnDwa` prefix before the original filename (i.e., `F23342_N004.fits` >>> `efmslCcnDwaF23342_N004.fits`). The resulting data is the basic processed data with individual frames (not per pointing) corrected for detector and instrumental effects.

5.10 The pipeline processor (Blue-Box): bluebox.coadd wrapper Module

5.10.1 The Blue-Box Co-Add Wrapper

It has not yet been decided whether an additional post-pipeline processing module will be released to the users. The pre-requisite for the IRC data reduction team is at present solely to deliver basic science grade processed data to the users. It is not the responsibility of the team to provide modules to produce mosaiced images or to provide tools for photometry, etc..

The output of the green box produces the basic processed data for individual frames. Additional processing is required to produce the basic science grade processed data. There exists

a jitter between frames in the IRC images causing frames to become unaligned with each other (note this is not an intentional dither which is a separate procedure). The attitude of these frames must be matched (for any shift and rotation in position) and stacked. This processing is carried out by the modules called from the Blue-Box pipeline (Note this is not the same as actually running the Blue-Box Post-Pipeline processor). In reality, this process occurs automatically at the end of the Green-Box pipeline processor. In order to do this, bright sources (stars) are extracted from each frame as source lists. These source lists are then used to calculate the shift and rotation for each frame looking at a particular field-of-view on the sky using the first frame as a reference.

The processing currently consists of the following steps almost entirely included in the blue-box *co-add* wrapper module;

- **Co-add individual frames: (bluebox.coadd)**

This module calls further individual modules to coadd the image frames together. There is also an alternative module that may be called to coadd the image frames for MIR-L using the information from the MIR-S channel in the case that there are not enough bright stars for an independent calculation of the shift and rotation of each frame.

- bluebox.source_extract: Extracts bright reference sources
- bluebox.calshift: Calculate shift and rotation value between image frames
- bluebox.adjust_sky: Adjusts sky level between individual frames
- bluebox.irc_stack: Stacks the IRC images

- **bluebox.putwcs:** To add WCS information to an image FITS file by matching 2MASS catalog coordinates.

The present configuration of the Blue-Box *co-add* wrapper module is shown in Fig 5.10.12.




Figure 5.10.12: Present configuration of the Blue-Box *co-add* wrapper module.

The starting point for the Blue-Box Co-Add wrapper are the files created from the final step in the Green-Box pipeline Processor `efms1CcnDwaF23342.S004.fits`. The Co-Add module then performs the following tasks:

1. **Extract bright reference sources: (bluebox.source_extract)**

This module extracts individual bright sources from individual frames. Before extraction, original 412x512 NIR images are paseted to larger 1024x1024 images to prepare for the xy shift and rotation. During source extraction, a "S" will be added such that `fdms1CnDaF23342_N004.fits` becomes `Sfdms1CnDaF23342_N004.fits`. Bright sources (stars) are extracted from each frame as source lists.

2. **Calculate Shift & Rotation to match frames: (bluebox.calshift)**

The bright reference star source lists are used to calculate the relative shift and rotation values between individual image frames looking at a particular field-of-view on the sky using the first frame as a reference. After this shift and rotation process, the original frame file names will receive additional "R" prefixes such that `Sfdms1CnDaF23342_N004.fits` becomes `RSfdms1CnDaF23342_N004.fits`. There is a parameter *minmatch* that determines the minimum number of stars required for matching between 2 frames. If there are not enough stars then a warning will be given and a log file `coadd.failure` created containing the names of the processed frames that could not be combined. A log file `calcshift.log` is also produced listing the number of stars matched between and the corresponding *x* & *y* offset for included frames.

3. **: Adjust Sky Level: (bluebox.adjust_sky)**

The `bluebox.adjust_sky` module collects all frames looking at a given area on the sky and calculates the median sky from each image. Each calculated median value is then subtracted from each individual corresponding frame. From these median values an average sky brightness is calculated that is then re-added to all the frames. A log file is produced during this process with a name `skypair0002_N2.list_long` or similar. This file lists the frames looking at a given area on the sky with the corresponding mean, median and mode sky brightness and 1σ standard deviation. Those who want to subtract median box car filtered image instead of adjusting sky level should configure the following parametes by typing "epar adjust_sky" **before running pipeline**.

- `submeds` (boolean, yes or no, default=no):
Subtract median filtered sky?
- `rmmedsk` (boolean, yes or no, default=yes):
Remove median filtered image? Those who want to check box car median filtered image, set this parameter no.
- `x_box`: (integer, min=1, max=100, default=21):
x box car size
- `y_box`: (integer, min=1, max=100, default=21):
y box car size

The parameters `x_box` and `y_box` change the size of the median kernel.

After adjusting the sky level, the "R" prefix is removed and an "A" is added, such that `RSfdms1CnDaF23342_N004.fits` becomes `ARSfdms1CnDaF23342_N004.fits`.

4. **Image Stacking (Co-adding): (bluebox.irc_stack)**

Once every frame pointing at the same area of sky in the *irclog* list has been correctly matched and the sky brightness adjusted, every frame is stacked to produce the final co-added image. The FITS images and files created from the stacking process can be found within a new directory `stacked_IM`. The stacking process creates 3 files for any given filter position on the sky;

- A co-added image file (e.g. `1757132_N2_long.fits`).
- A noise map (e.g. `sigma1757132_N2_long.fits`)
- Summary File (e.g. `p11757132_N2_long.fits.pl`)




Figure 5.10.13: Example of final science grade data produced by the Green-Box and Blue-Box Co-Add Wrapper. *left* is the stacked image map. *right* is the corresponding noise map.

5. Convert to WCS coordinates: (`bluebox.putwcs`)

After the Co-add wrapper has been completed, the module `bluebox.putwcs` adds WCS information to the FITS images by matching with 2MASS catalog coordinates using the following procedure;

- source extraction of stars from the IRC image
- download 2MASS catalog for the observed area
- convert 2MASS RA DEC to the x'y' image coordinates
- match 2MASS x'y' coordinates with image xy coordinates

At this point there will be a list for extracted IRC stars corresponding to

```
star1 x1' y2' ra1 dec1 x1 y2
star2 x2' y3' ra2 dec2 x2 y2
.....
starN xN' yN' raN decN xN yN
```

for the matched stars. The module then calculates a transformation matrix (Nth-order polynomial) that will convert xy to RA and DEC. The module attempts to find the best fitting solution by increasing the order of polynomial from 2 to 4. Usually, the best result should be 2nd order, as long as the image has been corrected for distortion.

- (if matched) put wcs in the header

Note that it is possible to shorten the time to download the relevant 2MASS catalog by changing the download mirror in the toolkit file `irc/perl/get2mass.pl`. Find the line that determines the data server where the 2MASS catalog will be downloaded. The default is Tokyo, Japan. To choose the nearest server, un-comment the relevant *URL* and comment out *TokyoJapan*.

Note for multiple pointings and deep imaging data, many pointings of data may have to be co-added. In such cases, all the images must be rotated, and the toolkit will have to take care of this before co-adding.

The final result is the basic science grade images (see Figure 5.10.13).

5.10.2 Log files produced from the toolkit

In addition, there are various log files produced by the toolkit which are described below

- **coo Files** The `.coo` files e.g. `Sfdms1CnDaF23342_N004.fits.coo.1` are the results for robust source extraction that extracts x and y coordinates & robust photometry. One `.coo` file is created for each individual exposure frame. These files can then be used to calculate the shift and rotation of frames that are being co-added by matching bright stars in the extracted source lists.
- **Pair Files** The *pair* files collect together and list all (long and short) frames that point the same area of sky.

Taking the N3 band as an example the following files may be seen,

```
pair0001_N3.list
pair0001_N3.list_short
pair0001_N3.list_long
pair0001_N3.list_long.shift
pair0001_N3.list_long.shift.0
```

The `pair0001_N3.list` file lists all (long and short) frames that point at the same area of sky. The contents of the file are the original frame names (e.g. `F23343_N001`), IRC channel and the coordinates. The files `pair0001_N3.list_short` & `pair0001_N3.list_long` are extracted and segregated from `F23343_N001` on the basis of the exposure time (long or short exposure frames). The file `pair0001_N3.list_long.shift` lists the result of the coordinate matching before coadding. Each line entry in the file consists of a filename, x-shift(pix), y-shift(pix), rotation(deg) and the number of stars used for the shift & rotation angle calculation. For example;

```
fdmslnDwaF01001_N003.fits.coo.1 0.0 0.0 0.0 0
fdmslnDwaF01007_N003.fits.coo.1 19.25942609 -0.00474931 359.99288567 126
```

The values are calculated relative to the first frame listed in the file, such that the first entry is always `filename 0.0 0.0 0.0 0`.

There may also be an additional *pair* file `pair0001_N3.list_long.shift.0` which is almost the same as the `pair0001_N3.list_long.shift`, but it also contains detector information, as filename, detectorID, x-shift(pix), y-shift(pix), rotation(deg) and the number of stars used for the shift & rotation angle calculation, i.e.


```
fdmslnDwaF01001_N003.fits.coo.1 1 0.0 0.0 0.0 0
fdmslnDwaF01007_N003.fits.coo.1 1 19.25942609 -0.00474931 359.99288567 126
```

- **exp.input files** These files contain a list of all the pair files for all filters pointing at one position on the sky. There may be files for both the long `long_exp.input` and short `short_exp.input` exposure frames.
- **Skypair Files** These log file can be found inside the separate directory `logs`. This log file is produced during the adjustment of the sky level between frames (`bluebox.adjust_sky`)

with a name `skypair0002_N2.list_long` or similar. This file lists the frames looking at a given area on the sky with the corresponding mean, median and mode sky brightness and 1σ standard deviation.

- `calcshift.log` This log file can be found inside the separate directory `logs`. The `calcshift.log` file is the log file for the calculation of shift and rotation in the `bluebox.calcshift` process. Relative to the first frame in the pair file described above the log file gives the number of stars matched between 2 `.coo` files and the corresponding x & y offset for these frames. The `calcshift.log` file will also record any matching failures.
- `darklist.before`

5.11 Toolkit structure



5.12 Working on the output

Users will receive both the original raw data and processed data up to, but not including the co-add stage for the toolkit. The data is basic, processed with the default parameters of the toolkit and users are advised to re-process using the latest version of the IRC toolkit.

5.13 Limitations of the functionalities in the current version of the imaging toolkit

5.13.1 Instrumental characteristics and artefacts in the data

- **First frame effect:** The first frame of the dark current prior to the pointing observation shows larger values than others. This effect could be related to the detector temperature.
- **Increase of hot pixels:** The number of hot pixels is increasing along the mission. They should be corrected when coadding individual images or correcting the image by its own dark image.
- **Memory effects:** No noticeable effects have been reported
- **Dark Level:** The dark level is not stable during the pointing observations. The NIR dark level shows no correlation with temperature.
- **Effects of high energy particle hits:** The toolkit does not perform any deglitching. Glitches should disappear when coadding individual images (median filter). Even so, their effect on the responsivity are not yet well investigated. Future versions of the toolkit will involve a more careful treatment of cosmic ray hits.
- **Ghosts:** Ghosts originating from the beam splitter are recognized. The positions, which depend on the real source positions, are well determined for all detectors and also depends on the filter. The intensity of the ghosts is well determined (a few %).
- **Background Level:** The background level changes during the pointing observations in all bands. It is due to the Earth shine reflection, therefore it depends on the angle between satellite and Earth and the epoch of the observation. The effect from the Earthshine is worse at northern ecliptic latitudes during June, July & August. The Background level is different at the beginning and at the end of the observation (see Fig 5.13.14), at different pointings (see Fig 5.13.15) and in different seasons (strongest in solstices). Note that the latter figures are in the MIR, but similar variations should be present in the NIR.
- **Earthshine in imaging observations:** Data taken in May, June and July may suffer from the Earthshine problem. The following recipe should be used:
 - Check the drift of the background level during a pointing and comment out any high background frames from “irclog” and run the pipeline again.
 - use `rej_sky=yes` option in order to ignore the bad frames:
`cl> pipeline rej_sky=yes`
 - use `submedsky` option to remove the diffuse background:
`cl> pipeline submedsky=yes # use for point sources only...`
 - adjust the median kernel size in the `submedsky` option:
`bluebox> epar adjust_sky`
`(x_box = 20)` If `submedsky=yes`, `x` box car size

(y_box = 20) If submedsky=yes, y box car size

- **Problem with short exposure frames with IRC:** At present no reliable estimate of the sensitivity in the short-exposure frame data is obtained. They can be used to check the saturation in the long-exposure frame data, but should not be used to derive the flux of bright objects.




Figure 5.13.14: Change in the background level in a pointing observation

5.13.2 Toolkit Limitations and Caveats

5.14 Error messages when running the pipeline and Troubleshooting

1. The pre-pipeline stage sometimes give an error message such as `ls: ../rawdata: No such file or directory` or `cat: slice_tmp0: No such file or directory`, etc, although the pre-pipeline seems to run correctly. Typing `unlearn_all` should clear these error messages.




Figure 5.13.15: Background levels

- The distortion processing (green box processing) can give the following error message, causing the pipeline crash:

```
### DISTORTION ###
Making the input file list...
Correcting distortion...
#This may take a while...
ERROR on line 56: Cannot open file
(~/iraf/irc/lib/distortion/DARK_distortion_database.dat)
distortion (ircconst=constants.database, logfile=irclog, prefix=mslnDwa,
verbose=no)pipeline ()
This is because the DARK entries should be removed from the irc log file.
```

- The coadd stage can result in the following error:

```
### COADD ###
Making the input file list...
Extracting sources...
Calculating XY shift...
Adjusting sky level...
Coadding images...
```

ERROR on line 148: parameter 'direction' not found

This problem may be caused when using versions of *IRAF* earlier than IRAF 2.12.2. The problem is with *geoxytran* task. *eparimages.immatch.geoxytran* can be typed in the *IRAF* shell to see if the parameter exists. Even after installing the newer version of IRAF it is necessary to type `unlearn geoxytran` before the toolkit runs correctly.

4. The pre-pipeline run can apparently miss some perl scripts and end with an empty or non existing *irclog* file.

```
### MKIRCLOG ###
```

```
Making the file list...
```

```
Reading header...
```

```
#This may take a while...
```

```
tcsh: ~/iraf/irc/perl/formatlog.pl: Command not found.
```

```
tcsh: ~/iraf/irc/perl/checkname.pl: Command not found.
```

```
### MKIRCLOG finished!! ###
```

Primarily, it has to be checked that the toolkit is being run from the working directory and not, for example in `~/iraf/`. If the problem persists then it may be because *perl* is in the wrong place! *Perl* should be in `usr/local/bin/perl`, therefore a symbolic link should be set up from the perl library to `usr/local/bin/perl` (type *whichperl* to find out where *perl* is currently hiding).

5. If a new version of the toolkit crashes, as a first fix, `unlearn_all` should be typed within *irc*.
6. The IRC toolkit does not run on the new Intel Mac machines, due to differences in the IRAF build in the intel binaries. Replacing the intel binaries with the original binaries causes *iraf* to run under emulation but solves the problem. IRAF 2.13 has been successfully run on the intel machines.
7. The coaddition process or the `coaddLusingS` function, can cause the crash of the toolkit with the error:


```
ERROR on line 128: Attempt to access undefined local variable 'filter'.
```

 This error will occur if the pre-pipeline is attempted to run twice on a given data set. As a check the files listed in the pair file should be examined to see if they have the appropriate "FILTER" keywords in their header.
8. The "Matching failed" error message that could appear in the `putwcs` process is not an intrinsic pipeline error. It is due to the fact that the 2MASS data format changes from time to time. Appropriate updates or patches are made to the pipeline. The updates will be recorded in the Observer's page.

Chapter 6

Spectroscopy pipeline cookbook

The spectroscopy pipeline is being developed and maintained by the IRC spectroscopy data reduction team. It is mostly written in IDL, and uses the IDL ASTRO library (maintained at the GSFC) among others. Although it is developed under Linux environment, it may be portable to other platforms after some modifications (though we have no plan to increase the exportable platforms by ourselves). The toolkit also uses the `ds9` FITS viewer, and the `xpa` package for communication between the `ds9` and the IDL main program.

The spectroscopy data reduction requires a calibration database (FITS images and ascii tables) distributed and updated by the IRC spectroscopy data reduction team. The database is based on observations of calibration objects and calibration frames taken during PV/DT phase observations, as well as pre-launch calibration experiments in our laboratory. Therefore observers do not have to make their own calibration observations.

The reduction of the data of phase 3 observations requires special care and tips. The new pipeline software (`IRC_SPEC_TOOLKIT_P3`) has been developed for the phase 3 data reduction, which is designed to work also for the phase 2 data. However, at the present, the verification of `IRC_SPEC_TOOLKIT_P3` has not yet been completed. It is recommended that `IRC_SPEC_TOOLKIT_P3` should be used exclusively for phase 3 data, whereas for phase 2 data the previous `IRC_SPEC_TOOLKIT` be employed. It should also be noted that the basic usage of `IRC_SPEC_TOOLKIT_P3` is exactly the same as `IRC_SPEC_TOOLKIT`. We provide special commands in `IRC_SPEC_TOOLKIT_P3` to work with phase 3 data. Therefore, in the followings the chapters for the phase 2 data reduction remain, which include those not relevant to the phase 3 data reduction, such as MIR-S and MIR-L data reduction. Users who are interested only in the phase 3 data can skip those descriptions. In addition, a chapter special for the phase 3 data reduction is added at the end (section 6.9). Users who work on the phase 3 spectroscopic data should read this chapter carefully.

6.1 General overview of the pipeline processing

The main pipeline processing consists of several well defined steps, which are explained in the following sections.

In general terms, the IRC slitless spectroscopy differs from more standard slit spectroscopy in that in the latter case, the pixel position and the wavelength are closely correlated. The IRC spectroscopy does not follow this relation and needs to be applied in three steps:

- Many spectroscopic flats have been combined to form a "super-flat" which can be used to remove the pixel to pixel variation of the monochromatic response of the detector.
- After subtracting the background, extracting the sources and performing the wavelength calibration, the wavelength flat can be used. The wavelength dependency of the flats

is due to the same mechanism to that of imaging mode, and is corrected by interpolating/extrapolating the imaging super-flat taken with two different filters for every pixel and the wavelength (colour correction).

- Finally, the spectral response specific to the spectroscopic mode observation is corrected by the spectral response function obtained from the observations of standard stars. More detailed explanations can be found in following subsections.

6.1.1 Dark subtraction

Scaled super-dark images are subtracted from the raw data. For the scaling, dark count offset is calculated within the pipeline, by comparing average counts at the slit-mask-covered portion of the pre-dark image, and the corresponding area on the super-dark image.

Additionally the average dark counts of the mask-covered portion of each observed sub-frame is measured, except for LG2 for which there is no good dark area on the spectroscopy images for measuring the dark level. The averaged offset is added to (or subtracted from) the super-dark to make the scaled super-dark.

6.1.2 Linearity correction/Saturation Masking

Linearity correction is made following the method adopted for imaging data reduction.

The saturation masking is also performed as in the imaging pipeline: the toolkit first checks the short-exposure images, and find regions where expected counts in longer-exposure frame exceeds the saturation limit based on the exposure time ratio of short-/long-exposure frames (see table 4.6.2). Then, the regions are masked in the longer-exposure frames. The user should check the masking in the edges of the saturated regions, due to the drift between short and long exposures pointing.

6.1.3 (monochromatic) Flat-fielding

In the case of the slit-less spectroscopy, the entire FOV is the aperture for the background sky, but the object image itself is the aperture for the object. This aperture size difference makes difficulties in flat-fielding the slit-less spectroscopy images since, unlike a conventional long-slit spectrograph, a given pixel can be illuminated by background photons with a range of wavelengths within the disperser's passband, and the mixing fraction of photons of different wavelengths depending on the spatial distributions and spectra of sources. We need 3D flat information (X, Y along space, plus Z along the wavelength) for full flat calibration. However it is impossible to obtain such a detailed flat since there are no good monochromatic flat light nor a series of narrow-band filters covering the passband of the disperser. Because of these difficulties, we will make a flat calibration in two steps, starting with the monochromatic correction.

To correct for the pixel-to-pixel variation of the monochromatic response (response or flat that does not depend on wavelength), the whole image is divided by the 'super-flat'. The super-flats are made by combining a larger number of background spectroscopy images. Note that the background sky image is not flat along Y or the wavelength axis, i.e., there are several spectral features on the 'super-flats' due to, e.g., contributions of zero-th or higher-order light in cases of grism spectroscopy images. Although the features should be removed to correct for the pixel-to-pixel variation of the response, we first divide the dark-subtracted images by the super-flat with the spectral features. As shown below in equation 6.1.1, this process makes the background flat, facilitating the sky subtraction.

Assume that the dark-subtracted images are represented by the following equation:

$$obs = sky \times F_1(x, y) \times spectral_feature(x, y) + obj(\lambda) \times F_2(x, y, \lambda) \times R(\lambda) \quad (6.1.1)$$

where $F_1(x, y)$ is the flat in which the background spectral features are not present, $F_1(x, y) \times \text{spectral_feature}(x, y)$ is the 'super-flat', $F_2(x, y, \lambda)$ is the wavelength-sensitive flat (see below for color-term correction), and $R(\lambda)$ is the spectral response. Since the super-flat is only a function of the position in the detector, this step is called monochromatic flat-fielding. If we divide the observation by the 'super-flat', we obtain:

$$obs' = sky + obj(\lambda) \times F_2(x, y, \lambda) \times R(\lambda) / [F_1(x, y) \times \text{spectral_feature}(x, y)] \quad (6.1.2)$$

6.1.4 Background subtraction (from individual sub-frames)

After monochromatic flat-fielding, the background should be flat over the aperture. However, in real data, this is not occurring in most of the cases. For NP, NG, and SG1, outlier-tolerant low-order polynomial surface fitting is performed for each sub-frame, and is subtracted off from the flat-fielded images. For SG2 and LG2, background suffers from straylight (from the Earthshine) contamination, and the flat-fielded images are much more structured. To make good sky subtraction, a median running-box filter is applied to estimate the local sky, and is subtracted off from the 'stray light-covered' background. Such background should be removed from individual sub-frames, since the contribution of the Earthshine depends on the telescope pointing angle from the earth direction, and the amount of straylight changes within a single pointing maneuver (or within a single AOT operation).

In the first pass of the processing within the pipeline, source masking will not be applied in determining the background, because no source position information is available at the stage. In the second pass, after processing through section 6.1.9 once, the background is measured again while considering the source masks.

The image obtained after background subtraction has the following expression:

$$obs'' = obj(\lambda) \times F_2(x, y, \lambda) \times R(\lambda) / [F_1(x, y) \times \text{spectral_feature}(x, y)] \quad (6.1.3)$$

6.1.5 Image screening

Some sub-frames may be severely damaged by cosmic-ray shower, a satellite passing in front of the telescope, etc. If this is the case, one can interactively set the flag, by using `ds9`, for any sub-frames to be discarded in the following processes.

6.1.6 Image registration (among sub-frames)

Relative image shift due to satellite attitude drift among spectroscopy sub-frames is measured by means of cross-correlation technique. This can be made only with NP and NG due to the number of spectra present in NIR images. For SG1, SG2, and LG2, pixel offsets measured with NP/NG are used for matching, rather than measuring their own shifts, since all cameras take images simultaneously.

Similar shift-and-add technique is also needed for the reference sub-frames, except for N3, where there is only a single reference sub-frame. To find the shift values for L18W, we first detect point sources in S9W, measure their positions, and calculate the shift by using the list of target coordinates, and shift both S9W and L18W images.

6.1.7 Imaging stacking

After registering all the sub-frames, all the selected (screened) sub-frames are combined to make higher S/N stacked images. For spectroscopy images, a three-sigma clipping averaging method

is used. For reference images, a simple median averaging is used due to the small number of sub-frames.

Some sub-frames are removed due to satellite maneuver. When the toolkit recognizes that the last exposure frame (cycle) was taken during this maneuvering period, the frame is automatically removed from the stacking list. Note that, although the observing manual says that 8 sub-frames will be taken for spectroscopy in AOT04 operation, it turned out that one additional frame (9th frame) can often be taken without suffering from satellite maneuvering. You may add the frame for stacking.

6.1.8 Target detection/position measurement

Target positions can be provided by the user in the form of a source table (see below), or automatically computed within the toolkit, using the `daofind` method for target detection. Even if the target positions are set by users, the toolkit performs re-centering of the source positions by means of Gaussian peak search. (This functionality can be disabled with the command line option.) This process is coupled with the following step (background subtraction).

6.1.9 Background subtraction (from stacked image)

Although background subtraction has been already applied before stacking images, any remaining background is removed at this step.

The background subtraction and target detection/position measurement (explained in the previous section) are made iteratively in the following way. First, the target is tentatively detected by the automatic source detection program (not based on the user-supplied source table), and source masks will be created for all detectable sources. Then the background is measured while considering the source masks, and is subtracted off from the original stacked image. The background-subtracted image is used for better source detection/position measurement, and better source masks will be created for better background subtraction.

When sources are detected, source masks are created for better background subtraction from individual sub-frames (section 6.1.4) in the second pass of the pipeline processing.

6.1.10 Extracting 2D spectra

By using the reference image positions and pre-defined coordinates offsets in the calibration database, rectangle areas around the source spectra are extracted on the spectroscopy images. For NP, spectral distortion (see below) is taken into account along the dispersion direction to find best Y offset when extracting 2D spectra.

X-offset adjustment in spectroscopy image extraction

In real data, one need to further adjust the offset of the source extraction boxes. One may sometimes find 2D spectra slightly away from the expected position (at the center of the extraction box) along X axis. This kind of shift cannot be corrected in the previous image registration processes, and the correction is made at this stage. The center position of the 2D spectra is measured for each extracted 2D spectra, and the mean X offset from the center of the extraction box is calculated. If the pipeline successfully finds the shift value, the shift will be applied in extracting the 2D spectra. However, for some cases where only very faint objects were detected, calculating this additional shift may fail (and no further shift is applied).

Measuring the X offset and making good source masks (as explained in the previous section) are closely related to each other during the pipeline processing. In the first pass of the source detection, the automatic source detection sub-program works even if the target table is supplied

in the pipeline command line. The X offset is measured with the tentatively detected sources at this stage. In the second pass, measured X offset (as well as Y offset found in adjusting the wavelength zero reference point; see the next section) between spectroscopy and reference images is taken into account in extracting the 2D spectra. Only the sources specified in the source table, or sources detected with the sub-program, will be processed (extracted) in the second pass. This two-stage process ensures good source masking for better sky subtraction and good offset measurement with brighter and larger number of sources, even for the cases in which the observer is only interested in small number of faint sources.

Measurement of the center position of the 2D spectra can be made easily for NP, NG, and SG1 spectra for which larger number of brighter sources can be detected even in blank sky regions. Therefore, the toolkit measures the X offset at NP and NG for correcting both NP and NG, and at SG1 for correcting SG1, SG2, and LG2. Therefore, the user must start pipeline processing for NP/NG first, then SG1, and finally SG2 and LG2. See section 6.4.1 for more explanations.

6.1.11 Wavelength calibration

In the case of grism spectra, the dispersion equation is almost linear theoretically and a linear equation for expressing the wavelength is assumed. Therefore, once the 2D spectra extraction is made with sufficient accuracy, it is straightforward to make a wavelength calibration.

For prism (NP) spectra, since the dispersion equation is highly non-linear one especially at shorter wavelength end, it is better not to transform images to avoid introducing extra uncertainties in the image interpolating/extrapolating processes. Rather, a separate array (whose length is equal to the Y length of the extracted 2D spectra) will be created to store the wavelength values for each Y pixel. One wavelength array is applicable for all the extracted spectra within the FOV. This kind of wavelength array is also used for grism spectra (NG/SG1/SG2/LG2).

Finding wavelength zero reference point

Some problems arise for accurate wavelength determination. One is the satellite attitude stability problem. If the satellite pointing moves between reference and spectroscopy images, the reference image does not provide good wavelength zero reference point any more.

The NP spectrum (before flux calibration) shows a notable peak around $2.4 \mu\text{m}$, and there are lots of fairly bright stars with almost identical spectra, regardless of the type of stars within a single FOV. Therefore it is possible to find the best offset of the wavelength zero reference point, by measuring the NP peak positions with respect to the spectral template that was taken when the satellite attitude stability was good enough, by averaging the offsets measured for many stars. Once the offset is measured, extraction of the 2D spectra is made again, after considering the Y offset (as well as X offset as explained earlier).

The zero reference point is much difficult to be found in NG spectra, due to lack of notable spectral features before applying the flux calibration. Therefore, although the toolkit can estimate the reference point by examining the observed spectroscopy images, it is strongly recommended to check the zero-th order light images for more accurate wavelength calibration.

The chance of detecting zero-th order light image at significant level for SG1, SG2, and LG2 is not so large. Therefore the drift of the wavelength zero reference point is calculated by using the drift measured in NP or NG for MIR-S/L grisms, after correcting the pixel scale difference.

Another issue related to measuring the wavelength zero reference point is the finite pixel resolution. Although the source positions can be measured with an accuracy of less than one pixel size unit on the reference image, the extraction of 2D spectroscopy images can only be made on integer pixel number to avoid erroneous image interpolation. This means that a pixel error as large as ± 0.5 could be introduced in the wavelength calibration process if not corrected, and is not so small comparing with the full length of the dispersed spectroscopy images (~ 50

pixel). As a first-order correction, we shift both the wavelength array and spectral response curve, both of which should show rather smooth change along Y (or wavelength) axis, and not perform sub-pixel shifting of the images. As a result, since object positions change slightly among different pointing observations, the wavelength at the same Y pixel of the extracted 2D spectra (or the wavelength array) also changes with different pointing observations.

6.1.12 Flat color-term correction

The presence of significant color variation in the flat images can be found in the ratio images of the broad-band flats (e.g., S7 flat / S15 flat). Therefore, although monochromatic flat-fielding can flat the background, the object spectrum is affected by the color term of the sensitivity. The correction for this could be done after extracting the 2D spectra for each target and applying the wavelength calibration. However, since we have only two broad-band filters for MIR-S/MIR-L (S7 and S15 for MIR-S, and L15 and L24 for MIR-L) and three for NIR (N2, N3, and N4), we can derive only global trends of wavelength-dependence of the flats. (Note that the wide-band filters, S9W and L18W, are not suitable for deriving the color dependence of the flat within the spectral coverage of the channel). Two broad-band flat images are interpolated to estimate the flats for a given wavelength in the following way:

$$F_2(x, y, \lambda) = [F(x, y, \lambda_2) - F(x, y, \lambda_1)]/(\lambda_2 - \lambda_1) \times (\lambda - \lambda_1) + F(x, y, \lambda_1) \quad (6.1.4)$$

where λ_2 and λ_1 are effective wavelength for broad-band filters.

Therefore the color term in equation 6.1.3 is expressed as:

$$\frac{F_2(x, y, \lambda)}{\text{spectral_feature}(x, y) \times F_1(x, y)} = \frac{\left[\frac{F(x, y, \lambda_2) - F(x, y, \lambda_1)}{\lambda_2 - \lambda_1} \times (\lambda - \lambda_1) + F(x, y, \lambda_1) \right]}{\text{spectral_feature}(x, y) \times F_1(x, y)} \quad (6.1.5)$$

Therefore the color-term correction is calculated by two broad-band super-flats and one spectroscopy super-flat. Note that the product $F_1(x, y) \times \text{spectral_feature}(x, y)$ always appears together, i.e., we do not have to separate *spectral_feature* term from the 'super-flat'.

After the color-term correction the image is as follows:

$$\text{obs}''' = \text{obj}(\lambda) \times R(\lambda) \quad (6.1.6)$$

For the NG spectra with the point source aperture (Np), flat-fielding will be made in a similar way to the slit spectroscopy of diffuse sources, since the aperture size is much smaller than the size of dispersed spectroscopy images. For spectroscopy with NG at Np and other slit spectroscopy data calibration, the super-flat is normalized to be unity at each wavelength (or Y) pixel, and there are no spectral features in the flats. On the other hand, NG spectra at Nc will be reduced in the same way as for other slit-less spectroscopy.

6.1.13 (local) Background subtraction (from extracted 2D spectra)

Although the background has been subtracted and it should be close to zero at this stage, any remaining background on the extracted 2D spectroscopy images is subtracted at this stage. Here we consider source masks for better determination of the local background. The background is measured and subtracted off, assuming a constant value across the images for all dispersers.

6.1.14 Spectral tilt correction

Although we do not reform the image 'shape' along the wavelength direction during the course of wavelength calibration because of simple linear grism dispersion, we do reform along X (or space) direction to correct spectral tilt. The tilt occurs due to misalignment of grism insertion direction with respect to chip orientation. The tilt is notably seen in NG images in which a pixel shift as large as $\Delta X \simeq 2$ is observed over the longer dispersed image length ($\Delta Y \simeq 250$ pixel). Similar tilt is also observed for other prism/grisms (NP, SG1, SG2, and LG2), although the tilt looks very small due to short dispersed image length. However, a tilt correction will be made for spectra of all types of dispersers.

6.1.15 Spectral response calibration

The spectral response calibration $R(\lambda)$ depends exclusively on the wavelength. Therefore the response calibration table is a 1D vector (λ vs. ADU/s/mJy). This means that response variations of individual pixels have been removed beforehand by flat-fielding processes. Being different from the spatial flat correction, the spectral response varies significantly with wavelength due to change in quantum efficiency of chip and change in optical transmission along the camera optical trains, including the disperser.

The observed wavelength-calibrated 1D spectrum in ADU is just divided by the spectral response table. Since the wavelength for a given pixel in the observed spectrum is slightly different from that in the response table, simple interpolation will be performed to match the wavelength of the observed wavelength-calibrated spectrum with that in the response table.

The spectral response function used in the pipeline was defined at the centre of the field of view and checked at the periphery of the field for consistency.

6.1.16 Notes on slit spectroscopy

The same pipeline can be used for both slit-less and slit spectroscopy data reduction. Although the reduction of the slit spectroscopy data can be made in a similar way as for the slit-less spectroscopy data, there are some differences in some processing steps between the two. Here we summarize these differences.

- The slit spectroscopy flat-fielding consists of a normalized feature-less flat image. Therefore no color-term correction is necessary.
- Background subtraction is made on extracted 2D spectra in the case of point sources slit spectroscopy (Np), after stacking sub-frames. If dealing with slit spectroscopy for diffuse sources, the background subtraction is not performed since entire slit is expected to be filled with the object that is diffuse and there is no pure background area in the image.
- Shift-and-add feature of sub-frames will be disabled. Therefore any spectral change along the slit could not be related to a real change in the spatial dimensions of the extended source in case of large telescope jitter motion is observed. To measure such motion, run the pipeline for slit-less mode (without any slit-processing option in the pipeline command).
- In the wavelength calibration, measurement of the reference image positions will not be made, and pre-defined slit positions will be used as a wavelength zero reference point.

6.2 How to install and to set-up the IRC spectroscopy pipeline

The package has been tested in a Linux environment. It seems to run on the MAC OS-X environment, though it is not officially supported.

- Ask you local computer administrator for the IDL installation. There are no special requests in the IDL installation.
- Ask you local computer administrator for the `ds9/xpa` installation. There are no special requests in the `ds9/xpa` installation.
- Get the `irc_specred` package from the AKARI Observer's web site (see section 1.2). Extract and store it under your favorite directory.
- Set the following environment variables in your command-line shell. Below is an example for `csh`:

```
setenv IRC_SPECRED_ROOT <somewhere>
setenv IRC_SPECRED_LIB ${IRC_SPECRED_ROOT}/LIB/
setenv IRC_SPECRED_HOME ${IRC_SPECRED_ROOT}/ASTRO-F/
setenv IRC_SPECRED_CALIBDIR ${IRC_SPECRED_HOME}/IRC_SPECRED/CALIBDIR/
setenv IRC_SPECRED_DATADIR <anotherwhere>
setenv IDL_PATH +<IDL system path>:+${IRC_SPECRED_HOME}:+${IRC_SPECRED_LIB}
```

`IRC_SPECRED_ROOT`, `IRC_SPECRED_DATADIR`, and `IDL_PATH`, have to be modified by substituting `<somewhere>`, `<anotherwhere>`, and `<IDL system path>`, according to your local system settings ¹.

6.2.1 Data preparation

As explained in Chapter 3, when de-packing the data from the archive under `IRC_SPECRED_DATADIR`, the raw data will be stored in `IRC_SPECRED_DATADIR/<targetid>.<targetsubid>/rawdata`. `IRC_SPECRED_DATADIR`, `<targetid>`, and `<targetsubid>` will be used in the command line of the pipeline command.

All the reduced data and related information will be stored in a separate directory called `<root_dir>/<targetid>.<targetsubid>/irc_specred.out`. When the directory is missing, the toolkit will create it.

6.3 Calibration data

When de-packing the toolkit, the following calibration directories are created:

6.3.1 Calibration files

- `${IRC_SPECRED_CALIBDIR}/DARK` contains dark images with high S/N, combined with pre-compiled dark images, which can be applied for all the observations, after performing a small correction in the count offset. There are several 'super-darks' for NIR/MIR-S/MIR-L (as specified in the following list files).

- `DARK/DARK_NIR_long.lst`, `DARK/DARK_NIR_short.lst`
- `DARK/DARK_MIRS_long.lst`, `DARK/DARK_MIRS_short.lst`
- `DARK/DARK_MIRL_long.lst`, `DARK/DARK_MIRL_short.lst`

- `${IRC_SPECRED_CALIBDIR}/FLAT` contains two types of flats: super-flats for spectroscopy and reference images. These super-flats are made by combining a large number of blank sky images:

¹In the following, contents within the parentheses `<something>` should be changed according to user's interests.

For slit-less spectroscopy:

- FLAT/SPEC2DFLAT_NP.lst
- FLAT/SPEC2DFLAT_NG.lst
- FLAT/SPEC2DFLAT_SG1.lst
- FLAT/SPEC2DFLAT_SG2.lst
- FLAT/SPEC2DFLAT_LG2.lst

For slit spectroscopy:

- FLAT/SPEC2DFLAT_NP_slit.lst

For reference images and color-term correction of the flats:

- FLAT/IMAG2DFLAT_N3.lst
- FLAT/IMAG2DFLAT_N4.lst
- FLAT/IMAG2DFLAT_S7.lst
- FLAT/IMAG2DFLAT_S9W.lst
- FLAT/IMAG2DFLAT_S11.lst
- FLAT/IMAG2DFLAT_L15.lst
- FLAT/IMAG2DFLAT_L18W.lst
- FLAT/IMAG2DFLAT_L24.lst

- $\{\text{IRC_SPECRED_CALIBDIR}\}/\text{MASK}$ contains images of known bad pixels (hot pixels, cold pixels, etc.). Masked area are marked by NaN (Not a Number) in the mask images.

- MASK/SLITMASK_NIR.lst
- MASK/SLITMASK_MIRS.lst
- MASK/SLITMASK_MIRL.lst
- MASK/OUTLIERMASK_NIR.lst
- MASK/OUTLIERMASK_MIRS.lst
- MASK/OUTLIERMASK_MIRL.lst

- $\{\text{IRC_SPECRED_CALIBDIR}\}/\text{COORDOFFSET}$ contains a table of coordinate offsets in pixels (dX , dY) used to extract spectroscopy images for each object based on target positions on the reference image for all dispersers. The table also includes sizes of source extraction boxes (ΔX , ΔY) on reference and spectroscopy images, and offsets (dX , dY) for zero-th order light image position.

- COORDOFFSET/IRCCOORDOFFSETPAR.dat

- $\{\text{IRC_SPECRED_CALIBDIR}\}/\text{WAVEPAR}$ contains the wavelength calibration tables.

For gratings (NG/SG1/SG2/LG2), the wavelength (μm) is expressed by a 1st order polynomial (linear) equation, and parameters are (1) dispersion ($d\lambda/dY$), (2) wavelength at origin (λ_0), and (3) position of the origin (Y_0). In the toolkit, the position of the origin is fixed at the center of the extracted spectroscopy image. Therefore, only dispersion and wavelength at the origin are set in the calibration database files. The parameters can be applied for all

the spectra within the FOV (i.e., the parameters are constant across the FOV). Effective wavelength ranges for each disperser are also set in the table (there are two kinds of range definitions: 'sensitive' and 'reliable' ranges).

For NP, the pixel position for a given λ is expressed in a 2nd-order polynomial equation, defined through three parameters (0th, 1st, and 2nd-order coefficients). Note that, for data analysis convenience, the equation is in $\text{pixel}=\text{function}(\lambda)$ form, being in inverse form for the grisms. Effective wavelength ranges are also set in the table.

Only for NP, significant spectroscopy distortion exists, i.e., reference positions on the spectroscopy images cannot be represented by a constant pixel shift (dX , dY) from reference image positions. The deviation of pixel shift along wavelength axis (or Y axis) from the case of constant pixel shift is expressed in 3rd-order polynomial equation of reference position ($dY_{\text{distortion}}=\text{function}(X_{\text{ref}}, Y_{\text{ref}})$). Polynomial coefficients are tabulated in a separate ascii table, and are stored under the same directory. Note that spectroscopy distortion along X ($dX_{\text{distortion}}$) is not so significant, and constant pixel shift works rather well for NP, as in the same way for NG/SG1/SG2/LG2.

- WAVEPAR/IRCWAVEPAR_COMMON.dat
- WAVEPAR/IRCWAVEPAR_NP.dat
- WAVEPAR/IRCWAVEPAR_NG.dat
- WAVEPAR/IRCWAVEPAR_SG1.dat
- WAVEPAR/IRCWAVEPAR_SG2.dat
- WAVEPAR/IRCWAVEPAR_LG2.dat
- IRCSPECBOXDYPAR_NP.dat

- $\{\text{IRC_SPECRED_CALIBDIR}\}/\text{RESPONSE}$ contains ascii files tabulating λ vs. ADU/long exposure time in seconds/mJy for each disperser. There are five such tables (NP/NG/SG1/SG2/LG2). The spectral response is measured by observing flux standard stars with known flux energy distribution. This directory also contains a NP template spectrum (wavelength-calibrated spectrum, before calibrating spectral response) that will be used to find relative image shift along dispersion direction (or Y) between spectroscopy and reference images.

- RESPONSE/RESPONSE_NP.lst
- RESPONSE/RESPONSE_NG.lst
- RESPONSE/RESPONSE_SG1.lst
- RESPONSE/RESPONSE_SG2.lst
- RESPONSE/RESPONSE_LG2.lst

- $\{\text{IRC_SPECRED_CALIBDIR}\}/\text{DISTPAR}$ contains ascii tables containing spectral tilt information of the grism insertion angle.

- DISTPAR/IRCDISTPAR_NP.dat
- DISTPAR/IRCDISTPAR_NG.dat
- DISTPAR/IRCDISTPAR_SG1.dat
- DISTPAR/IRCDISTPAR_SG2.dat
- DISTPAR/IRCDISTPAR_LG2.dat

- $\{\text{IRC_SPECRED_CALIBDIR}\}/\text{APCOR}$ contains the spectral aperture correction tables.

- APCOR/APCOR_NP.dat
- APCOR/APCOR_NG.dat
- APCOR/APCOR_SG1.dat
- APCOR/APCOR_SG2.dat
- APCOR/APCOR_LG2.dat

6.4 Running the pipeline

6.4.1 Data reduction order

The pipeline has to be run more than once, for NP (AOT0a) or NG (AOT0b) first, then SG1 and SG2, and finally LG2. We need to start processing the shorter wavelength cameras (NIR and MIR-S), where larger number of brighter sources are expected to be observed within the FOV as position reference sources. The information derived there will be used for registering the longer wavelength cameras (MIR-S and MIR-L).

- to measure relative X and Y shift among spectroscopy sub-frames of NP/NG for registering spectroscopy sub-frames of NP/NG/SG1/SG2/LG2.
- to measure relative X and Y shift among reference sub-frames of S9W (with larger number of brighter sources) for registering imaging sub-frames of S9W and L18W.
- to measure relative X and Y shift of the spectroscopy image with respect to the reference image of NP or NG for registering reference and spectroscopy images of NP/NG/SG1/SG2/LG2.

Therefore the data reduction order should be as follows:

- First run: run the pipeline for NP (AOT04a) or NG (AOT04b), without a target table for enabling automatic target detection sub-program.

For NG data with point source aperture (Np), one needs to run the pipeline first without /Np_spec option. For other types of slit spectroscopy, one may skip this run because shift-and-add feature is disabled for this observing mode.

- Second run: run the pipeline for your desired targets. Make target tables for N3, S9W, and L18W on the raw images (at this stage only N3 image has been processed). Run the pipeline again for NP/NG/SG1/SG2/LG2 with target lists. Image shift database created previously with NP/NG will be used for the 2nd run. If your target is compact and bright enough to be detected by the source detection sub-program, you do not have to perform this 2nd run. For the 2nd run, begin processing for NP/NG first, then SG1, and finally LG2.
- Third run: run the pipeline again if you want to revise the target table. This is optional. Now you got processed reference images for revising the target tables. Run the pipeline again with the updated target tables to see final results.

6.4.2 Running the pipeline

Type the following in the IDL command line (a command in a single line):

```
irc_specred, <targetid>, <targetsubid>, <ext_source_table>, <refimage_list>,
<specimage_list>, <filter_spec>
```

Mandatory arguments:

- **targetid**: ID of the pointing observation. The information will be provided with the data distribution.

Example: 1331048

- **targetsubid**: Sub-ID of the pointing observation. The information will be provided with the data distribution.

Example: 1

- **ext_source_table**: An ascii list describing source position (X, Y) in pixel, or the target table.

Example: myobjects.tbl

```
cat myobjects.tbl
 100.0 100.0
 200.5 200.5
 150.0 150.5
```

This will extract spectra of sources located at (100.0, 100.0), (200.5, 200.5), and (300.0, 300.5) in pixel on the reference image.

If **ext_source_table** is set to "" (null string), then the pipeline activates its sub-program for automatic source detection.

There are some important tips in preparing the source table:

- Coordinates counts from 1, not 0, i.e., coordinates of the lower left corner of the image is (1, 1), not (0, 0).
 - For NIR the toolkit interprets by default the pixel coordinates as measured in the raw image (before the image rotation). When one measures the source positions in the processed images (after the image rotation), set the **/rotated_NIR_source_table** option at the pipeline command line.
 - For MIR-L, one can use Y range of either 257-512 (for images before detaching MIR-S/L) or 1-256 (for images after detaching MIR-S/L) to set Y position of the targets. The pipeline subtracts 256 from the Y input if Y>256.
- **refimage_list**: An ascii file listing FITS file names of reference image.

Example: N3.lst

```
cat N3.lst
F000001_N.fits
```

A default list is provided with the data distribution, and is found in **/rawdata** directory.

- **specimage_list**: an ascii file listing FITS file names of spectroscopy images.

Example: NP.lst

```
cat NP.lst
F000002_N.fits
F000004_N.fits
F000006_N.fits
```

A default list is provided with the data distribution, and is found in **/rawdata** directory.

Even if you find some images being damaged severely and you do not want them to be included in the pipeline processing, you must list all the images in the input list. Then you

should specify the sub-frames to be removed on `ds9` within the pipeline. This is because the file names and their order in the list are used to relate FITS files to the exposure timing along the AOT operation sequence.

- `filter_spec`: a string specifying a disperser for the processing. Set one of the following: `N3_NP`, `N3_NG`, `S9W_SG1`, `S9W_SG2`, `L18W_LG2`

6.4.3 Options

- `root_dir`: a string specifying a directory in which a set of data is located. If set, this overrides the setting found in the environment variable `IRC_SPECRED_DATADIR`.
Example: `root_dir='/DATA/ASTRO-F/IRC/SPEC/'`
- `/Nh_spec`, `/Ns_spec`, `/Ls_spec`: flags for slit spectroscopy data reduction.
- `/Np_spec`: a flag for `Np` spectroscopy data reduction.
See section 6.1.16 for more information of slit spectroscopy data reduction.
- `/no_tune_sourcepos`: a flag for disabling source position tuning subprogram within the pipeline. By default, `irc_specred` tries to measure accurate source positions by searching Gaussian peak around the coordinates set in the target table. This flag disables this functionality.
- `/use_short_refimage`: use a short exposure image to measure source positions. By default, `irc_specred` uses the long exposure frame for measuring source positions in the reference image. With this flag set, the toolkit uses the short exposure frame for measuring the source positions. Note that the data reduction will be made for both short and long exposure frames even with this flag set. This flag could be useful for measuring source positions of bright and saturated objects in the long exposure frame.
- `savefile`: set this option to a named variable that will contain the file name of the IDL save file (section 6.5.5). The simplest way to restore the IDL save file is to run `irc_specred` with the `savefile=savefile` option, and issue `restore,savefile` command after `irc_specred` finished and before, e.g., plotting the spectra.
- `/no_slit_flat`: a flag for disabling flat fielding process for slit spectroscopy at NIR. By default, `irc_specred` performs spectroscopy flat fielding with the super-flat image. However, as the natural background is faint in the NIR, the quality of the flat can not be improved so much. As a result, unfortunately, the quality of the processed spectra is limited by the quality of the flat, not by the dark current nor photon noise. With this option set, `irc_specred` skips performing the flat fielding. Users are recommended to compare the spectra processed with and without the flat fielding process. We expect no big differences among the two spectra, except for random pixel-to-pixel variation of the flux, or some narrow (as narrow as one-pixel size) spike features, meanwhile spectra processed without the flat fielding could look better in terms of S/N. However, it seems a good idea to compare the results processed with and without the flat fielding. If you find that this is also the case for your data, you may adopt the data processed with the option `/no_slit_flat`.
- `/nir_column_pull_down_correction`: a flag for enabling masking column pulled-down regions in NIR images. With this option set, `irc_specred` searches for any pulled-down columns in each sub-frame, by examining dark area pattern at `Nh` slit area where background is minimum, and the pipeline masks out the columns. Furthermore, the pipeline also masks the same region in the next sub-frames in which damage by the column pull-down is still visible for deepest pulled-down columns.

6.4.4 Outputs

- Whole image products:
 - Processed and stacked reference image (and corresponding mask and residual (reference image \times mask) images). Dark subtraction, flat-fielding, and background subtraction are made:


```
<targetid>.<targetsubid>.<filter_spec>.refimage_bg.fits
<targetid>.<targetsubid>.<filter_spec>.refimage_mask.fits
<targetid>.<targetsubid>.<filter_spec>.residual_refimage_bg.fits
```
 - Processed and stacked spectroscopy image (and corresponding mask and residual (spectroscopy \times mask) images). Dark subtraction, flat-fielding, and background subtraction are made:


```
<targetid>.<targetsubid>.<filter_spec>.specimage_bg.fits
<targetid>.<targetsubid>.<filter_spec>.specimage_mask.fits
<targetid>.<targetsubid>.<filter_spec>.residual_specimage_bg.fits
```

These images are in 3D, being the third (Z) dimension for the short (Z=0) and long (Z=1) exposure frames.

NaN (Not a Number) represents masked pixel/area.

- Extracted image products:
 - Extracted reference images for individual targets:


```
<targetid>.<targetsubid>.<filter_spec>.refimage_bg_indiv.fits
```
 - Extracted spectroscopy images for individual targets (and corresponding mask images). There are two kinds of images. One is wavelength calibrated (`_WC`) image for which flat color-term correction and wavelength calibration were applied. The other are flux calibrated (`_FC`) images for which flux calibration was applied as well as flat color-term correction and wavelength calibration:


```
<targetid>.<targetsubid>.<filter_spec>.specimage_wc_indiv.fits
<targetid>.<targetsubid>.<filter_spec>.specimage_mask_indiv.fits
<targetid>.<targetsubid>.<filter_spec>.specimage_fc_indiv.fits
<targetid>.<targetsubid>.<filter_spec>.specimage_noisemap_indiv.f its
```

Note that our spectral plotting tool (see below) uses `_WC` image as an input, not the `_FC` image, since the tool does on-the-fly flux calibration after considering various plotting conditions/options. Since the default `_FC` images does not care these, we strongly recommend to use our plotting tool to review the spectra.

In `_wc_indiv.fits` and `_fc_indiv.fits` files, wavelength information is set in the FITS headers with header keywords: `CRVAL`, `CDELTA`, `CRPIX`, and `CD` matrix. Users can plot the spectra with, e.g., the standard spectral plotting tool `SPLIT` on `IRAF`.

Note, however, that there are no such FITS header information for prism NP spectra because of their non-linear wavelength solution.

Here is an example to plot the SG1 spectra with `IRAF/ SPLIT` task.

```
splot xxxxxxx.1.S9W_SG1.specimage_fc_indiv.fits
```

```
Image line/aperture to plot (0:) (1): 10
```

```
Image band to plot (1:) (1): 2
```

In this example, the plot shows flux-calibrated spectrum of the 2nd object along X (space) =10 pixel. Note that 2nd object means source ID 1 on the IRC_SPECRED since IDL counts from zero while IRAF does from one. Note also that no aperture correction can be applied for the spectral plot with the SPLIT task.

These images are in 3D, being the third (Z) dimension for source id. NaN (Not a Number) represents the masked pixel/area.

- Others:

- Target information table: a table of target information, such as positions (after source position tuning), flux, and size (Gaussian FWHM).

```
<targetid>.<targetsubid>.<filter_spec>.target_table.tbl
```

Its format is the following:

```
ID, image_x, image_y, image_mask_dx, image_mask_dy, spec_x, spec_y, spec_mask_dx,
spec_mask_dy, flux, image_FWHM, spec_bgnoise_ADU, spec_x_pos,spec_x_FWHM,
bad_sourcepos_flag
```

- Target table: If the source detection sub-program is used within the pipeline, a target table will be written. The file format is similar to the input target table. When source position tuning option is on, this file contains the updated source coordinates.

```
<targetid>.<targetsubid>.<filter_spec>.source_table.tbl
```

- IDL save file: The output of the pipeline will also be stored in the IDL save file, which is basically a dump file of the IDL memory image at the end of the pipeline processing. See also 6.5.5 to see how to work on the save file.

```
<targetid>.<targetsubid>.<filter_spec>.IRC_SPECRED_OUT.sav
```

- Log of the toolkit processing: a copy of the `irc_specred` logger is saved as an ascii file.

```
<targetid>.<targetsubid>.<filter_spec>.log
```

- DS9 region files: DS9 region files that have been used to locate targets on reference and spectroscopy images on `ds9`.

```
<targetid>.<targetsubid>.<filter_spec>.refimage.reg
```

```
<targetid>.<targetsubid>.<filter_spec>.specimage.reg
```

The region files and saved FITS images of the whole image products can be used to review the targets on `ds9` manually.

- Pipeline work files: The following files will be created by the pipeline. The files will be overwritten without notice. User are asked not to delete any of these files.

- `NP_SHIFT_XY.dat`: for registering NP/SG1/SG2/LG2 sub-frames in AOT04a

- `NG_SHIFT_XY.dat`: for registering NP/SG1/SG2/LG2 sub-frames in AOT04b

- `S9W_SHIFT_XY.dat`: for registering S9W and L18W sub-frames

- `NP_SPECBOX_SHIFT_X.dat`: for shifting SG2/LG2 along X in AOT04a

- NP_SPECBOX_SHIFT_Y.dat: for shifting the wavelength zero-reference point for NP/SG1-/SG2/LG2 in AOT04a
- NG_SPECBOX_SHIFT_X.dat: for shifting SG2/LG2 along X in AOT04b
- NG_SPECBOX_SHIFT_Y.dat: for shifting the wavelength zero-reference points of NG/SG1-/SG2/LG2 in AOT04b

6.4.5 Summary of interactive operations within the pipeline

Although the pipeline program works as a 'pipeline' (i.e., without interactive operation by users), some operations in the `irc_specred` do require interactive operation.

- Removing one or more sub-frames before combining the sub-frames: In some sub-frames, one may find severe damage by cosmic-ray shower, nearby satellite passing in front of the telescope, etc. To check the sub-frames and remove from the sub-frame combination list, all the dark-subtracted/flat-fielded/sky-subtracted sub-frames will be shown on a `ds9` for reviewing. To remove some sub-frames, use the **Frame** -> **show/hide frames** pull-down menu of `ds9` to hide the frame(s) you need to remove. The toolkit checks the hidden sub-frames and remove them from the internal sub-frame combination list.
- Retrying automatic source detection with modified detection parameters: If you use automatic source detection sub-program within the pipeline, you can retry source detection after tweaking the detection parameters. You will see the reference image on the `ds9` with detected sources marked, and you are asked to answer if the detection is satisfactory or not. If the answer is no, then another dialog with several detection parameter entries pops up. You can edit the parameters, and press OK to re-find the sources. You can repeat this detection process as many times as you like until you get satisfactory source list. The sub-program uses `daofind` algorithm, with the following parameters:
 - threshold: Threshold intensity for a point source - should generally be 3 or 4 sigma above background.
 - fwhm: FWHM to be used in the convolve filter.
 - sharplim: 2 element vector giving low and high cutoff for the sharpness statistic (Default: [0.2,1.0]). Change this default only if the stars have significantly larger or smaller concentration than a Gaussian.
 - roundlim: 2 element vector giving low and high cutoff for the roundness statistic (Default: [-1.0,1.0]). Change this default only if the stars are significantly elongated.

By default, threshold is three times the measured background noise. When too much or too less sources are found, threshold change would give better results, and it is not necessary to take care of sharpness/roundness parameters in most of the cases.

6.4.6 Warning messages of the pipeline

Some common and frequently appearing warning messages are listed below.

- **Warning (irc_specred): Wrong number of arguments!** Check the command line arguments, and try again.
- **Warning: No <..> was found/set...Stop!** Some files that should be provided for the pipeline seem missing. Check if list files are properly set in the command line. This warning will also appear if you run SG1/SG2/LG2 data reduction before performing NP or

NG data processing, and some mandatory database files, e.g., describing relative image shifts, are missing.

- **Warning: Offset search box is too small!:** When the telescope drifts too much, the image matching sub-program fails to find the best shift values among sub-frames. Normally the sub-program resumes searching the shift with larger search box. Normally, this message is not so serious.
- **Warning: No data are available for measurement... Returning 0! or Warning: Data seems too noisy (sigma=<sigma>)... Returning 0!:** These messages will appear if, e.g., detected sources are too faint and their positions could not be measured with good enough accuracy. Check the source detection parameters for better source detections. This message is not so serious in most of the cases.
- **Warning: sigma of specbox Y shift measurement seems too large!:** This warning appears when the toolkit fails to measure the relative Y shift of NP spectra with respect to N3 reference image. Check the reference image on ds9 to know if source detection could be made successfully. Sometimes the program might detect only cosmic-ray hits, not stars, if the parameters are not optimized.
- **Warning: sky level is larger than 1.5 times sky sigma!:** After extracting spectroscopy images, remaining sky will be subtracted off locally around the source. If everything works fine, the average of the remaining sky should be very small, and is typically less than 1.5 times sky rms fluctuation. This warning message will appear if sky level is larger than the typical value. When this warning appears, check the ds9 image to see if there remains large scale sky level variation. Presence of such sky often indicates failure in monochromatic flat-fielding and/or global sky subtraction, or any big unexpected debris. Note that this warning will not appear for slit spectroscopy (including NG at Np).
- **Warning: Available sky area is too small!:** Due to clouded source masking, the remaining sky area is too small for measuring sky. Check the source detection parameters for fewer source detection. Usually, this message is not so serious.
- **Warning: Cross-correlation peak is weak:** The cross-correlation function will be calculated while registering sub-frames and/or short and long exposure frames. The peak value of the cross-correlation function is a good measure of the frame registration. The value is 1 for ideal image matching, and is typically 0.6 or larger for real data with noise, but peak of 0.3 is still good. When this warning appears, check the quality of the registered and stacked images. So far registration of the short exposure frame can not be made with good enough accuracy, and one should ignore this warning for short exposure frames. This message is not so serious in most of the cases.
- **Warning: ROB_MAPFIT: Too few points!:** This message comes from the fitting routine ROB_MAPFIT called from some of the toolkit programs. The routine tries to fit the image region robustly (e.g., excluding outliers, iteratively, etc.), but it sometimes fails when the fitting area is heavily masked out for some reason. However, it somehow return the result (even if the results are not reliable in terms of statistics). Users may ignore the messages.
- **Warning: strange spec file list... Stop!:** The irc_specred reads list of FITS files to be processed (NP.lst/NG.lst/SG1.lst/SG2.lst/LG2.lst). When something wrong happens during data acquisition (i.g., too much time before stabilizing the telescope pointing), telemetry downlink (e.g., loss of telemetry), and/or data handling at ground (e.g., disk storage failure), the listed available FITS files are not in a proper order. Observers

may notice that the list misses one or more FITS files due to some of these reasons. The toolkit analyze the file list before actually processing the data, and warns the uses if it detects something strange. Upon this warning messages, users are requested to check the input file lists or contents of distributed FITS files, and report any problems to the AKARI/IRC Helpdesk for more support. Although the `irc_specred` skips this list checking routine if a flag `/no_database_check` is set to the toolkit, use of this option without noting problems is dangerous, and usually is not recommended.

6.5 Working on the pipeline output

6.5.1 Displaying the whole images on ds9

Here we explain the region marks on the `ds9` that are shown in the processed whole image products, e.g., spectroscopy and reference images before source extraction.

In the spectroscopy image side (left),

- The blue rectangle shows spectroscopy image extraction area.
- The green rectangle shows area reserved for the object (or masked area for other objects).
- The red rectangle shows plotting area as defined by the spectral plotting tool.
- The yellow circle shows the expected positions of the zero-th order light.

In the reference image side (right), marked circles correspond to source positions (with diameter of the source FWHM).

- Green circles show sources with good position measurements.
- Red circles show sources with less accurate position measurements.

Source identification numbers are also indicated by the region marks.

For clear view of the image under complicated region marks, check out the `region -> show regions` check box in the `ds9` pull-down menu.

To display these images manually, issue

```
show_aperture_on_ds9, <image>, source_table (,/imag) 2
```

where `<image>` could be `refimage_ff[*,*,1]` or `specimage.bg`, etc. on the IDL command line. When `/imag` option is set, the image is shown on the right side of the `ds9`, with region marks for reference image. The default (no option) is for spectroscopy image. See appendix for more on array name conventions.

6.5.2 Displaying the extracted images on ATV

ATV is a general-purpose interactive array image-displaying tool. The array should be in 2D. See ATV web page (<http://www.physics.uci.edu/barth/atv/>) for more information on the program ³.

Command line syntax:

```
atv,array(,/block)
```

Here are some ATV tips:

²Items in parentheses () are optional.

³In some systems, `/block` option may be required for interactive operation on the ATV. The conditions for which `/block` requirement seems to depend on local Linux or X11 system settings. The author does not have any good ideas on the correct usage of this option.

- To display whole images, issue
`atv,<array>[*,* ,1]`
 1 means long exposure frame (and 0 for short). Here, <array> should be something like `refimage_bg` or `specimage_bg`.
- To display extracted images of your desired `source_id`, use
`atv,<array>[*,* ,source_id]`
 Here, <array> should be something like `specimage_n_bg`. To check mask area, use
`atv,<array>[*,* ,source_id]*mask[*,* ,source_id]`
- When color table looks abnormal, type `set_color` at the IDL prompt before launching the `atv`.

6.5.3 Checking for wavelength zero reference point with the zero-th order light image

The toolkit calculates the wavelength zero reference point based primary on positions of the objects on the reference image. It also takes into account a wavelength zero-point drift due to satellite attitude drift, as well as coordinate rounding effect when extracting 2D spectra. In most cases, these methods work well to estimate the wavelength zero reference point with accuracy of 0.5 pixel or less. Since positions of the zero-th order light image are also calculated in the same way as for the wavelength zero reference point, one may check the wavelength zero reference point accuracy by comparing positions of expected zero-th order light image and actually observed ones. Unfortunately, this check can be made only when bright sources with measurable zero-th order light images are observed at some part of the FOV by chance.

When a shift is found, the `change_wave_offset` command can correct for the estimated wavelength shift in pixel. The shift is calculated from the current position. This command changes the internal variable that records the wavelength offset, updates an offset database on disk, and re-draws the images on `ds9` with updated zero-th order light marks. This command can be used as many times as needed until getting satisfactory result. Then one can use the spectral plot tool for reviewing spectra with updated wavelength and spectral-response calibration. See below for the plotting tools.

Command line syntax (a command in a single line):

```
change_wave_offset,<wave_offset>,source_table,
space_profile,spec_profile,wave_array,specimage_fc_1d,
refimage_bg,specimage_bg,
refimage_n_bg,refimage_n_bg_short,
specimage_n_sff,specimage_n_sff_short,
specimage_n_wc,specimage_n_wc_short,
specimage_n_fc,specimage_n_fc_short,
res_refimage_bg,res_specimage_bg,
mask_refimage,mask_specimage,mask_specimage_n,
imagerheader,specheader,imagerheader_extract,specheader_extract,
noisemap,noisemap_n,noisemap_short_n,noise_mask,
dir=!IRC_SPECRED_DIR.workdir,savefile=savefile,/write_indiv_spec
```

where <wave_offset> is a pixel number (e.g., 1.0, 0.5, -0.5) to be shifted. ⁴

⁴Since this is a very long command, it seems better to copy the command that is written in the `#{IRC_SPECRED_HOME}/IRC_SPECRED/irc_specred.pro` program.

6.5.4 Spectral plotting tool

The toolkit's spectral plotting tool can handle many IRC-spectroscopy-specific features, and we recommend to use it for creating spectral plots. These are some of the functionalities of the tool:

- source masks can be considered. (see also `/no_mask` option)
- error bars (statistical plus systematical ones) can be plotted.
- simple image filters for removing isolated 'spike' pixels can be applied.
- aperture stacking along spatial direction and smoothing along wavelength direction can be applied for higher S/N spectra.
- shifting aperture positions along spatial direction (X axis) can be made.
- aperture correction.

Command line syntax (a command in a single line):

```
plot_spec_with_image,wave_array,specimage_n_wc,mask_specimage_n,
source_table,<source_id>
```

and for short exposures:

```
plot_spec_with_image,wave_array,specimage_n_wc_short,mask_specimage_n,
source_table,<source_id>,/short
```

with the following options:

- **nsun**: Number of pixels along X axis combined for plotting. Default is 3. For slitless spectroscopy, larger **nsun** (wider aperture) collects more photons from the object, but this also collects more background noise. Therefore, the best **nsun** for highest S/N is typically 2 or 3 for point sources (corresponding typical full-width of image PSF). In the case of slit spectroscopy, the range to plot the spectrum is:
 - NP/NG: up to the edge of the extracted region
 - SG1: $\text{nsun} \leq 10$
 - SG2: $\text{nsun} \leq 8$
 - LG2: $\text{nsun} \leq 8$

If `space_shift` $\neq 0$ (see below) then the range should be smaller in order to prevent from extracting the spectrum out of the slit area.

- **smooth**: Boxcar smoothing width (in pixel) along wavelength direction. Default is `smooth=0` (no smoothing). For spectra with higher S/N without losing spectral resolution, `smooth` should be 3 (corresponding typical full-width of image PSF). Larger boxcar smoothing window will lose the spectral resolution. Note that when even number is set in the `smooth` (e.g., `smooth=2`), the actual smoothing box size would be `smooth+1` (e.g., `smooth=3`).
- `/sigma_filter`: This option enables `sigma_filter` operation (at 3 sigma significance level) over 2D spectra to remove spatially isolated high or low count pixels. Default is off. If you find too narrow emitting/absorbing features in your plots, try this option to see if this is a real feature or not. Note that, if there is a cosmic ray hit at the position in one of the sub-frames, such count should be removed as an outlier while combining sub-frames with sigma-clipping averaging method. However, if there are temporal hot pixels

or weaker hot/cold pixels that are not shown in the hot pixel mask database, you will find outliers (hot or cold pixels) even after sub-frame combination. Users should take care not to remove real narrow features.

- **space_shift**: shift of the plot extracting box along X (spatial) axis in pixel. Default is zero. Although the pipeline adjusts the X coordinates of spectrum extraction box by measuring positions of spectra, one may find remaining X offset in some cases. Change this offset to find peak position of the flux. If one changes **nsum** and **space_shift**, issue the display command to see the modified spectrum extraction boxes graphically on the spectroscopy images over the **ds9**.

```
show_aperture_on_ds9,specimage.bg,source_table,
space_shift=<space_shift>,nsum=<nsum>
```

(a command in a single line)

- **/no_mask**: by default, plots are shown after applying spectral overlapping masks by nearby sources. The **/no_mask** option disables this masking functionality and plot spectra regardless of the possible source overlapping. Since masks are created without examining the source brightness and/or spectral shape (e.g., line emitters, continuum emitters with break, etc.), one may often find the situation where no significant change in plots is found when comparing plots with and without the masking. If this is the case, you can just disable the masking by setting **/no_mask** option.

This option is especially relevant when the source of interest is much brighter than the overlapping ones.

- **ps, png, ascii**: Plots will be recorded on the files, not on the IDL plot window.
 - **ps=<filename>** creates a postscript file (**filename.ps**) of the plot in the working output directory (under **/irc_specred_out**).
 - **png=<filename>** creates a png image (**filename.png**) of the plot in the working output directory.
 - **ascii=<filename>** creates an ascii file (λ vs flux and flux errors) (**filename.spc**) of the plot in the working output directory. This file can be used for further analysis, for example using **gnuplot** program, with the command of **plot 'filename.spc' with yerrorbar**.
- **/with_image, tvbottom=<tvbottom>, tvtop=<tvtop>**: The 2D image will be shown on TV (an IDL graphic window) below the spectrum plot. Extraction box for plotting 1D spectrum is overlaid. The default is **with_image=0** (i.e., no TV display). The top and bottom ADU counts for displaying image can be specified with **tvtop** and **tvbottom**. These options are active only when **/with_image** is set.
- **/diffuse**: For slit spectroscopy data, spectra will be shown in units of MJy/str, rather than mJy with this option. The diffuse flux calibration is not yet fully established. Before this flux scale conversion, both **nsum** and **space_shift** parameters are taken into account to specify the spectral extraction aperture to create the spectrum for plotting.
- **/no_aperture_correction**: Aperture correction for point-like sources will be applied automatically within the plotting tool. The aperture size, set by **nsum**, is taken into account to find the correction factor. When the **/no_aperture_correction** option is set, the correction will be disabled. To perform good aperture correction, the aperture is centered on the source, and **nsum** should be 3 or more. Note that the aperture can be shifted by **space_shift** parameter.

- Other generic plot options useful in the plotting tool: The plotting tool accepts any kind of IDL-generic plot options for spectral plotting. See `plot` manual in the IDL documents for full information.

Following are some frequently used options.

- `xrange`: plot range along the X (wavelength) axis. By default, plots are shown within the wavelength range set in the wavelength calibration database file along the X axis. If set explicitly in the plotting tool command line, the default settings will be overridden.
- `yrange`: plot range along the Y (flux) axis. By default, plots are shown in auto-scale mode along Y. One can limit/fix the plot range by setting `yrange`.
- `/xlog`, `/ylog`: plotting in log scale along x or y.

6.5.5 Working on saved data

All the processed data are saved as an IDL save file, as well as FITS output files. The IDL save file is actually a dump record of the IDL memory image at the end of the data processing. Therefore, one can recall the pipeline results by simply issuing the following command: `restore,<savefile>`. Here the `<savefile>` is a string of the save file name. To recall other save file image, issue `.reset_session` first to clear the current IDL memory contents, and then issue another `restore` command with another save file name. See IDL manual to know more on the IDL save file, `restore`, and `.reset_session` commands.

After restoring the IDL memory, one can use, for example, the following `irc_specred` commands to review the results.

- `show_aperture_on_ds9, specimage_bg,source_table`
- `show_aperture_on_ds9, refimage_bg,source_table,/imag`
- `plot_spec_with_image,wave_array,specimage_n_wc,mask_specimage_n,source_table,<source_id>`

6.6 (Hopefully) Useful Tips

6.6.1 Getting best S/N spectra in slit (N_s , N_h) or N_p spectroscopy data

Due to the higher dispersion of NG spectra, through narrower slit area (N_p , N_s , N_h), at near infrared where the natural background light is faintest, the S/N of the NG slit flat image is rather poor, and this often limits the quality of the processed spectra. There is an option to disable the slit flat correction (`/no_slit_flat` option of `irc_specred`). We recommend processing the same data, with (default) and without (with the option) flat correction, for comparison. If one finds little noticeable differences in spectral features, (except for quality of the spectra), as we expect, one may accept the spectra processed without flat correction as a final calibrated data. See also section 6.4.3.

6.6.2 Tackling narrow spikes seen in NIR spectra (especially in slit spectra)

Even if one is interested in the slit area, any anonymous bright stars that happened to be within the big aperture may cause the column pull-down effect of the array, damaging even the slit spectroscopy data. To check this possibility, examine not only the 1D-extracted spectra but also

the entire 2D-images, even outside of the slit area, so as to locate damaged columns (or rows, since NIR images are rotated during the toolkit processing).

With the toolkit version 2, new option `/nir_column_pulldown_correction` was introduced, and the pulled-down columns will be masked out. See also section 6.4.3.

6.6.3 Examining strange/fake features in NP spectra, especially around 2.4-3.5 μm

Sometimes an error in wavelength calibration leads to errors in the spectral response calibration, creating funny/fake spectral features in NP. In this case, the features resemble the response curve (or more exactly, its change per pixel along wavelength). Because of lowest spectral resolution and rather structured response-curve shape, this effect is most clearly seen in NP spectra. Note that even small wavelength offset (say, a mere 0.5 pixel) would produce noticeable pseudo spectral features, especially around 2.4-3.5 μm . We recommend to check the spectra of nearby field stars as well as your object to see if the funny features are common to all objects. If they look similar, the features are likely to be fake.

To see how the features change with wavelength offset, try the procedure described in section 6.5.3. Although there are no zero-th order light images available for NP, the command `change_wave_offset` works even for NP for testing how the spectral features change with the offset. Note that, for NP, there are no guidelines, such as zero-th order light, to find the best wavelength zero point in general. Therefore the user should justify the amount of offset entered with this command. Remember that nominal error of the wavelength zero-point calculation is 1.0 pixel or less.

6.6.4 Examining flux level (in)consistency among different disperser data

Sometimes one may find jumps in flux level between SG1 and SG2 spectra (or other pairs of adjacent wavelength) for a single source. There are possible reasons for the jump, and tips to solve the problem.

- Source contamination: Degree of contamination changes with wavelength and, hence, with dispersers, causing flux change across the dispersers. User needs to check the reference image as well as spectroscopy images to find possible contaminating sources. There are no good recipes to remove the contamination.
- Aperture centering: Check the aperture position (along X or space) to see if the aperture is really at the peak of the dispersed images. The toolkit tries to put it at the right position by tracking the telescope jittering motion, but it is not always perfect. Use `space_shift` option of the plotting tool along with `/with_image` option to find the best position. See section 6.5.4 for actual operation.
- Aperture correction uncertainties: Aperture correction is not always perfect because one needs to adopt rather narrow aperture (`nsum=3` or so) for achieving the best S/N. If this is the case, even a small shift of the aperture position on sky (even at a scale of sub-pixel, although `space_shift` should be given in an integer pixel unit) gives rather large uncertainties in the flux aperture correction. Note that spectroscopy data relies on 1D spatial PSF of the source, and the pixel scale is not high enough to sample the PSF at good enough accuracy. So, with these limitations in mind, one needs to check the flux level, by changing the `nsum` and/or `space_shift` parameters, for your own source and its brighter neighbours, to find the accuracy of the absolute flux calibration. See section 6.5.4 for actual operation.

- **Wavelength offset error:** Because of the very low spectral resolution, the spectral response curves show rather sharp change near the band edge. If the wavelength offset is not properly set, a systematic error in the flux level is expected near the band edge due to wrong wavelength assignment in the spectral flux calibration process. If this happens, the spectrum looks brighter and fainter (or fainter and brighter) at the shortest and longest wavelength coverage of the disperser in a systematic manner. The way the shape change depends on the sign of error in wavelength offset (plus or minus). See section 6.5.3 for checking the wavelength offset error.

6.7 Appendix

6.7.1 Variable name conventions

As a general rule, the extension of the IDL variables (`_ff`, `_bg`, `_wc`, `_fc`) indicates the finally processed calibration status. Examples:

- `_ff` means that the data is processed all the way to flat-fielding.
- `_bg` means that the data is processed all the way to background subtraction, i.e., flat-fielded and background subtracted.
- `_wc` means that the data is processed all the way to wavelength calibration, i.e., flat-fielded, background subtracted, and wavelength calibrated.
- `_fc` means that the data is processed all the way to flux calibration, i.e., flat-fielded, background subtracted, color-term corrected, wavelength calibrated, and flux calibrated.

Whole image products: `_ff` and `_bg` are in 3D format (X, Y, short/long ID). Short exposure frame is in Z=0, and long exposure frame is in Z=1.

Extracted image products: `_n_` images are in 3D. The third dimension is for indicating the source id. The following extensions refer to different processing stages:

- `_n_bg`: background subtracted on extracted images.
- `_n_wc`: wavelength calibrated, after color-term corrected, residual background subtracted.
- `_n_fc`: flux calibrated, after color-term corrected, residual background subtracted, and wavelength calibrated.

Finally, these are the most frequently referred arrays:

- `refimage_bg`: Flat-fielded, background-subtracted whole reference image in 3D (X, Y, short/long ID)
- `specimage_bg`: Flat-field, background-subtracted whole spectroscopy image in 3D (X, Y, short/long ID)
- `specimage_n_wc`: Wavelength calibrated extracted 2D spectra in 3D (X, Y, source_id)
- `specimage_n_fc`: flux calibrated extracted 2D spectra in 3D (X, Y, source_id)

6.7.2 Summary of Commands and their Options

This is a broad outline of the main commands related to the pipeline together with their general syntax. For arguments encompassed by `<>` and `<>`, you need to specify your own processing parameters. Options starting with `/` are flags or switches to enable some functionality of the routine. For other options, you can set your parameters in numerals or ascii characters (that should be encompassed with single quotations).

- Running the pipeline

Usage:

```
irc_specred, <targetid>, <targetsubid>, <ext_source_table>, <refimage_list>,
<specimage_list>, <filter_spec>
```

Options

- `<targetid>`: pointing id of your observation. Typically, '1234567'. Check your data distribution.
- `<targetsubid>`: pointing sub-id of your observation. Typically, '1'. Check your data distribution.
- `<ext_source_table>`: an ascii file that specifies the source coordinates in X and Y in units of pixels. If this is set to be " (null), then automatic source detection program will be enabled within the pipeline.
- `<refimage_list>`: an ascii file that specifies the FITS file names of the reference images to be processed. Typically, either 'N3.lst', 'S9W.lst', or 'L18W.lst'
- `<specimage_list>`: an ascii file that specifies the FITS file names of the spectroscopy images to be processed. Typically, either 'NP.lst', 'NG.lst', 'SG1.lst', 'SG2.lst', or 'LG2.lst'
- `<filter_spec>`: an code to specify the data processing mode, or a pair of filter and disperser names for the processing. This should be one of the following: N3_NP, N3_NG, S9W_SG1, S9W_SG2, or L18W_LG2.
- `/Nh_spec`, `/Ns_spec`, `/Np_spec`, `/Ls_spec`: flags to specify the slit spectroscopy data reduction.
- `/no_tune_sourcepos`: a flag to disable source centering functionality (fine tuning of source positions with local Gaussian fitting around the user-specified source locations) when the toolkit is run with user-specified source table.
- `/use_short_refimage`: a flag to use short reference image, rather than long reference image, for source detection. This is good for bright, saturated sources.
- `/no_slit_flat`: a flag to disable flat-field correction for slit spectroscopy data (for `Np_spec`, `Ns_spec`, `Nh_spec`, `Lc_spec`). Use of this switch is recommended for slit spectroscopy with the current version of the toolkit/calibration database.
- `/nir_columnpulldown_correction`: a switch to enable correction for column pull-down effect for `Np` spectra.
- `savefile`: an ascii variable that store the file name of the IDL save file that records the `irc_specred` output.

- Displaying whole image products

Usage:

```
show_aperture_on_ds9, specimage_bg, source_table
```

or

```
show_aperture_on_ds9,refimage_bg,source_table,/imag
```

options

- `nsun`: width of source extraction apertures in units of pixel, corresponding to the width of red rectangles shown on `ds9`.
- `space_shift`: number of pixels by which to shift the source extraction apertures along spatial direction.
- `/imag`: a flag to display reference images. Without this flag, the procedure assumes that the data to be displayed are spectroscopy images.

- Plot spectra

Usage:

```
plot_spec_with_image,wave_array,specimage_n_wc,mask_specimage_n,  
source_table,<source_id>
```

options previously:

- `<source_id>`: a number that specify the source to be plotted. You can find the number by looking at the `ds9` window that displays whole image products.
- `/short`: a flag to display short-exposure spectra. One needs to set `specimage_wc_short`, instead of `specimagen_n_wc` in the `plot_spec_with_image` command.
- `nsun`: number of pixels along X axis combined for plotting. This `nsun` parameter also works for `/diffuse` option.
- `smooth`: boxcar smoothing width (in pixel) along wavelength direction.
- `/sigma_filter`: a flag to enable `sigma_filter` operation (at 3 sigma significance level) over 2D spectra to remove spatially isolated high or low count pixels.
- `space_shift`: shift of the plot extracting box along X (spatial) axis in pixel.
- `/no_mask`: a flag to disable masking functionality, i.e., plotting spectra regardless of the possible source overlapping.
- `ps`: root filename of the PS graphical output (`<ps>.ps`) of the spectral plot.
- `png`: root filename of the PNG graphical output (`<png>.png`) of the spectral plot.
- `ascii`: root filename of the ASCII numerical output (`<ascii>.spc`) of the spectra.
- `/with_image`: a flag to display 2D image below the spectral plot.
- `/diffuse`: a flag to convert flux scale to MJy/str for slit spectra.
- `/no_aperture_correction`: a flag to disable aperture correction factor in plotting the spectra.
- `xrange`, `yrange`: parameters to specify plot ranges in X and Y axes, respectively.
- `/xlog`, `/ylog`: a flag to plot spectra in logarithmic scale along X and Y axes, respectively.

- Tweak wavelength zero-point manually

Usage:

```
change_wave_offset,<wave_offset>,source_table,  
space_profile,spec_profile,wave_array,specimage_fc_id,
```

```

refimage_bg,specimage_bg,
refimage_n_bg,refimage_n_bg_short,
specimage_n_sff,specimage_n_sff_short,
specimage_n_wc,specimage_n_wc_short,
specimage_n_fc,specimage_n_fc_short,
res_refimage_bg,res_specimage_bg,
mask_refimage,mask_specimage,mask_specimage_n,
imagheader,specheader,imagheader_extract,specheader_extract,
noisemap,noisemap_n,noisemap_short_n,noise_mask,
dir=!IRC_SPECRED_DIR.workdir,savefile=savefile,/write_indiv_spec

```

– `<wave_offset>`: offset along wavelength direction in pixel units.

6.8 Error messages when running the pipeline and Troubleshooting

- In general **double quotation mark (“)** can cause problems when calling the toolkit in IDL. For example:

```
restore,"12345678_some_more_information.sav"
```

or

```
irc_specred,"12345678_some_more_information.tbl",'SG1.lst','SG2.lst','S9W_SG 1
```

give IDL syntax error, We suggest to use ' (single quotation mark), rather than " (double quotation mark) anytime when you work with the IRC_SPECRED toolkit. For more, check the IDL manual (search 'quotation').

- When **one of the input parameters of the toolkit is a null string**, no space between single quotation marks should be given. For example:

```
irc_specred,' ','SG1.lst','SG2.lst','S9W_SG1'
```

will give an error message, because the toolkit tries to find the source table whose name is ' ' (blank space), and it fails. The correct syntax is:

```
irc_specred','','SG1.lst','SG2.lst','S9W_SG1'
```

- If **IDL complains about some undefined procedures/functions**, probably something is wrong in the setting:

– Check `.cshrc` carefully, and/or.

– After launching the IDL, issue `print,!path` on the IDL command line. This command shows all the paths for the IDL to search the libraries. See if all the TOOLKIT directories are included in `!path`.

- If after running the pipeline several times successfully, it fails with some unknown reasons, try resetting the IDL session, by issuing `.reset` command at the IDL command line. This resets everything stored in the IDL memory, including IDL common and environmental variables that are referred/updated during the toolkit session. Some old settings might cause the trouble. We recommend to reset every time the toolkit is restarted after a pipeline processing failure to avoid any confusion regarding old IDL variables. Remember, however, that the `.reset` command will destroy even the main IDL memory contents that contain information for, e.g., plotting the spectra. Of course, users can restore the IDL save file contents back to the main IDL memory to resume the data analysis.

- The filename where the toolkit saves the information is always `<targetid>.<targetsubid>.<filter_spec>.IRC.SPECRED_OUT.sav`. Therefore the `savefile` is a string variable output that records the save file name, not an input to specify the save file name. If the pipeline is run more than once with different options, the savefile should be renamed before the second run in order to be able to recover the previous results. You can recall the record even if you rename the save file name, by issuing:
`restore,<renamed_save_file>.`
- If you want **to see the results of previous toolkit run**, recalling the save file, and you do not remember the ID of your source, issue:
`show_aperture_on_ds9, <image>, source_table, (/imag)` as instructed at section 6.5.1. This launches a `ds9` and displays image and region marks on it. Do not forget to include `source_table` after `<image>`.
- **There are no good ways to run more than two pipeline processes** at a same time on a single computer as a single user, because more than two toolkit processes share some same `ds9` windows. Please use other computers or other user account.
- There are no good tools to **coadd data taken over multiple pointings**. This is beyond the purpose of the toolkit right now. The simplest way is to average/combine extracted 1D spectra after dumping the results on ASCII files, with the `ASCII` option of the `plot_spec_with_image` command and coadd them with any available tool. Note that the wavelength for a given pixel is different from pointing to pointing for slit-less spectroscopy data, even if the same target was observed with the same pointing coordinates. One may need to rebin the spectra for a common grid for proper stacking.
- There are no good tools for **plotting spectra for a given source taken with different dispersers at once**. One needs to dump the spectra with the `ASCII` option when plotting the individual spectra, and then use your favorite plotting software for plotting multiple spectra once.
- **If the spacecraft attitude shifts after the reference frames have been taken**, the effect will be apparent in the wavelength calibration. A shift of more than 1-2 pixels can happen. For NP only, the signal at the peak of the RSF is used to correct the wavelength reference by default. The result will be inserted into the log file which will be further used to correct the drift in `SG1/2` and `LG2`. Therefore the NIR data should be processed first. Similarly, for NG in the point source aperture (Np), the NG slitless spectroscopy field should be processed first. The actual correction is made by shifting the wavelength array rather than the image array.
- **Strange features found in the NG spectra taken at Np aperture** can be due either to flat-field problem or column pull-down. See section 6.6.1 or 6.6.2.
- **Strange features in the NP spectra taken with the big aperture (for Nc pointing)** will be due to wrong calibration only if the features are seen not only in your target object but also in nearby field stars. See section 6.6.3 for more information.
- There are several kinds of difficulties in **matching the flux level of the same source across the dispersers**, especially in slit-less spectroscopy mode, and jumps in flux level can be found between spectra from different dispersers in the same source. See section 6.6.4 for more details.

- If **unexpected narrow emission-line objects are found**, it could be due to zero-th order light images of nearby brighter stars. See the `ds9` window carefully since it shows the expected location of such features with yellow circles.

6.9 Tips for the Phase 3 data reduction

The evaluation of the phase 3 data is ongoing. Here we summarize the caveats and tips of the phase 3 data reduction. In the phase 3 data reduction special options are prepared to deal with the saturation of the reference image.

6.9.1 AOT IRCZ4

In phase 3, 5 dark frames are taken before and after the observations of your target. The observation sequence is the same as in phase 2: 4 spectroscopic observations, one reference imaging with N3, and 4 spectroscopic observations.

In phase 3, the number of hot pixels increases significantly. To secure redundancy, automatic dithering scheme is implemented for multi-pointing observations both for slit-less and slit observations. For Np observations, the pointing position is shifted by 3 arcsec in the X or Y direction, whereas 6 arcsec shift is executed for Nc. For Ns and Nh slit observations, a shift of 4 arcsec in the X direction is executed in multi-pointing observations.

6.9.2 Spectroscopic performance

The telescope image quality is degraded in phase 3 by 10% (Onaka et al. 2008). This leads to a degradation in the spectral resolution of the slit-less, including Np, spectroscopy as well as the revision of the aperture correction. In most case, the degradation in the resolution is not significant except for the region shorter than $2.5\ \mu\text{m}$ with NP, where the calibration becomes more difficult. However, no change in the spectral response and spectral dispersion is noticed.

According to the change of the point spread function, a new aperture correction table is provided for phase 3.

6.9.3 Dark current, linearity, and hot pixels

In phase 3, the dark current is increased and the number of hot pixels is also increased significantly. To accommodate these changes, the array operation was adjusted, which reduces the saturation level significantly (see the Imaging cookbook). A new linearity correction, which is the same as for imaging observations, is applied to phase 3 data.

The decrease of the saturation level makes observations at Nc with NP at high background regions (low ecliptic latitude regions) very difficult. The background level becomes very close to the saturation and only a small amount of the dynamic range for point sources is left.

Because of the increase of hot pixels, dark images created from the 10 dark observations before and after the target observations in the same pointing is applied in the phase 3 data reduction. The toolkit for phase 3 have several options to deal with this situation (see section 6.9.5), such as the usage of short-exposure frames to detect point sources in the slit-less modes (Nc and Np).

6.9.4 Response

No change is noticed in the relative spectral response in phase 3. However, the absolute sensitivity is estimated to be 70% of the phase 2 based on observations of the standard stars. This

is compatible with the result of imaging observations. The 0.7 factor is included in the phase 3 toolkit.

On the other hand, there is a problem unclear at present in the absolute calibration in short-exposure frame data. Therefore short-exposure data cannot be used to estimate the flux accurately.

6.9.5 New options for the phase 3 data reduction

In `irc_specred` we have the following new options.

- `/use_short_refimage`: This option allows the program to use the short-exposure image for the detection of point sources when they are saturated in the long-exposure image.
- `/no_long_saturation_mask`: This option dismisses the saturation mask for long-exposure frames. This option is useful for high-background observations, where the frame-to-frame shift measurement fails with the mask. Try this option if you found unrealistic values in the X or Y shifts between frames.
- `/use_short_for_wave_offset`: This option allows the program to determine the zero-point of the wavelength in the short-exposure frame. This option works in a similar way for the spectroscopic images to `/use_short_refimage` for the reference image data.

Try this option if the software cannot measure the zero-point of the wavelength.

- `/short_saturation_mask`: With this option, the saturation mask of short-exposure frames of spectroscopy data is used to calculate the wavelength offset. This is applied only for the spectroscopic data.

For the phase 2 toolkit, the saturation mask is applied only for long-exposure frames.

Similar saturation masks cannot be applied to the short-exposure reference image because saturated pixels are treated as hot pixels and corrected by interpolation. In the present software there is only one mask data, which include hot pixels and saturated pixels.

- `/use_short_for_calc_x_shift`: This option allows the software to determine the shift between the spectroscopic images and the reference images from the short-exposure frames. With too many hot pixels, it becomes difficult to determine the shift and this option may be useful.

For `plot_spec_with_image` we have the following option for the phase 3 data reduction.

- `median = 3`: Whereas the shift-and-add process reduces the number of masked pixels in slit-less observations, the reduction of masked pixels is not expected for slit observations (N_s and N_h) and hot-pixel masked pixels are often seen in the final stacked image. With the option `median = 3`, the data are median-averaged in the spatial direction to make up the masked pixels. This will be useful for observations of extended sources, but it is introduced only to make the spectrum look better. For scientific purposes, users should apply more sophisticated methods.

6.9.6 Installation and usage of the toolkit for phase 3

The installation of the toolkit is the same as that for phase 2 except that the software will be installed in the directory `irc_spec_toolkit_p3`. You should set the path to this directory. To start the toolkit, it is the same as for phase 2 for the observation of 12345678.1 (obsID.obs#) as

```
IDL>irc_specred,12345678,9,"N3.lst","NG.lst","N3_NG", root_dir="dir/"
```

No change is needed also for `plot_spec_with_image`.

The toolkit automatically recognizes AOTZ4 data from the FITS headers.

The software `irc_specred` should be executed without any new options first and follow the same sequence as for the phase 2 data.

If your sources are too bright and saturated in long-exposure reference image, then use the option `/use_short_refimage`.

If you find that a large fraction of the area is saturated in the long-exposure frames of the spectroscopic images, try the options `/use_short_refimage`, `/no_long_saturation_mask`, `/short_saturation_mask`, `/use_short_for_wave_offset`, `/use_short_for_calc_x_shift`.

6.9.7 Known problems

Some of the problems described below should hold also for phase 2 data.

- As describe above, the absolute flux calibration for short-exposure frames is still under investigation. It is different from that can be expected from the difference in the integration time from long-exposure data. At present the cause is not yet fully understood.
- New flats for spectroscopic image data of phase 3 are not yet ready. New flats will be provided in the future. For slit observations (Ns and Nh), it is still recommended to use the option `/no_slit_flat`, which give better S/N spectra in most cases.
- Although we confirmed the spectral performance (dispersion) is not changed in phase 3 and no change has been applied in the relative spectral response, the calibration of NP data shorter than $2.5\ \mu\text{m}$ may be changed with a large uncertainty because of the worse PSF of the telescope in phase 3. Users should use NP spectra shorter than $3\ \mu\text{m}$ with special caution.
- The wavelength calibration for the shortest end of NG ($2.5 - 2.6\ \mu\text{m}$) has a systematic error of a pixel ($\sim 0.05\ \mu\text{m}$). For longer wavelengths no systematic deviation is seen so far. This problem is under investigation.
- The calibration of NG for wavelengths longer than $4.9\ \mu\text{m}$ has an error due to the overlap of the second-order light. In the present calibration, the data of blue standard stars are used. Therefore, it is underestimated and red sources often show a decline at the end of the NG spectrum. This is not a true feature. Since this is a problem originating from the second-order light, there will be no recipe to correct for it for objects that have different colors from standard stars.